









estos ProCall Attendant Console

8.1.1.7387

1	Welcome to estos ProCall Attendant Console	7
2	What estos ProCall Attendant Console is able to offer you	8
2.1	 Contact search: Find information about the current contact.	8
2.2	 ActiveContacts - actively manage contacts.....	8
2.3	 Presence – see the availability of your contacts	8
2.4	 Federation - The trustworthy network.....	8
2.5	 Journal - tracking and planning communication.....	9
2.6	 Audio/VideoChat - Realtime communication using WebRTC	9
2.7	 Computer Smartphone Integration via Bluetooth (CSPI)	9
2.8	 Softphone - Making phone calls with the PC via a PBX.....	9
3	Installation and Base configuration	10
3.1	Installation	10
3.1.1	Requirements	10
3.1.2	Installation at the workplace	11
3.1.3	Installation via update service	12
3.1.4	Installation using group policies	12
3.2	Base configuration.....	13
3.2.1	ProCall Attendant Console language.....	13
3.3	Licenses	13
3.4	Lines	14
3.4.1	TAPI-driver	14
3.5	Base configuration	14
3.5.1	ProCall Attendant Console language	15
3.5.2	Connection to the server	15
3.5.3	User authentication	16
3.5.4	User settings: general user information	16
3.5.5	User settings: contact address and user profile picture	17
3.5.6	User settings: phone numbers.....	17
3.5.7	User settings: services.....	18
3.5.8	Groupware connection.....	19
3.5.9	Exchange Web Services	20
3.5.10	Start options.....	21
4	Usage of existing contact data	22
4.1	Supported data sources	22
4.2	Data from IBM Notes®	23
4.3	Cooperation with Microsoft® Outlook/Exchange	23
4.3.1	Joint data usage	23
4.3.2	estos ProCall Attendant Console Plug-in for Outlook®	24
4.4	Google integration	25

5	Work with estos ProCall Attendant Console	26
5.1	Program start and overview	26
5.1.1	estos ProCall Attendant Console start and shut down.....	26
5.1.2	Login account	26
5.1.3	Main window	27
5.1.4	Menu bar icon	29
5.1.5	Speech bubble info	30
5.2	Manage contacts	31
5.2.1	Search contacts	31
5.2.2	Contact details.....	34
5.2.3	Telephone number formats.....	35
5.2.4	Authorizations	36
5.2.5	Favorites.....	44
5.2.6	ActiveContacts	44
5.2.7	The Phone-Link.....	46
5.3	Use presence information	47
5.3.1	Own presence	47
5.3.2	The presence of the contacts.....	49
5.3.3	Presence icons	50
5.4	Plan communication.....	51
5.4.1	Journal.....	51
5.4.2	Journal browser	52
5.4.3	Journal editor.....	55
5.4.4	Unprocessed calls and chat	56
5.4.5	Call planning	57
5.4.6	Reminder window	59
5.5	Communicate.....	60
5.5.1	Call window	60
5.5.2	Line settings	66
5.5.3	Call forwardings	66
5.5.4	Remote Office	67
5.5.5	Chat, SMS, E-Mail	67
5.5.6	Audio-/Video conversation window.....	69
5.5.7	Screen Sharing.....	72
5.5.8	Set up voicemail box	73
6	Customise estos ProCall Attendant Console.....	74
6.1	Appearance and behavior	74
6.1.1	View	74
6.1.2	Characteristics	75
6.1.3	Actions	76

6.1.4	Action filter	78
6.1.5	Action fields	80
6.1.6	User-defined actions	85
6.1.7	Hotkeys	87
6.1.8	Shortcuts	88
6.1.9	Location	88
6.2	Location	89
6.2.2	Advanced.....	90
6.2.3	PBX system.....	91
6.2.4	Least cost routing	92
6.2.5	Projects	94
6.2.6	Check rules	96
6.2.7	Area code rules	97
6.2.8	Dialing prefix rules	97
6.2.9	Location concepts.....	98
6.2.10	Formatting rules.....	101
6.2.11	Vanity	102
6.3	Regular expressions.....	103
6.3.1	Advanced.....	104
6.3.2	Dialog adaptation with Templates.....	104
6.3.3	Function control via Windows® Registry	105
6.4	Telephony	107
6.4.1	Conversation window.....	107
6.4.2	Incoming calls	108
6.4.3	Outgoing calls.....	108
6.4.4	Planned calls	108
6.4.5	Projects	109
6.4.6	Bluetooth.....	110
6.4.7	Call Protection	112
6.5	Search.....	112
6.5.1	Data sources	112
6.5.2	Search parameter	116
6.5.3	Search result	117
6.6	Integration	117
6.6.1	Calendar	118
6.6.2	Journal.....	118
6.6.3	DATEV integration - Automatic Data Transfer.....	119
6.7	Services	119
6.8	Notifications.....	119
6.9	E-Mail dispatch.....	121

6.10	SMS dispatch	122
6.11	XSL templates	122
6.12	XSLT for e-mail notification	122
6.13	Configuration file location	123
6.14	Collaboration.....	125
6.14.1	Chat	126
6.14.2	Notification window	126
6.14.3	Audio/Video Wizard.....	127
7	Info about estos ProCall Attendant Console	132




1 Welcome to estos ProCall Attendant Console

The user help available leads you through the installation, configuration and handling of estos ProCall Attendant Console.

- An overview of basic functions is shown on the page What estos ProCall Attendant Console offers to you.
- Install estos ProCall Attendant Console and make the most important settings: Installation and Base Configuration.
- Information about how to integrate your contacts in estos ProCall Attendant Console Usage of existing contact data.
- Everything about the daily work with the programme can be found under Work with estos ProCall Attendant Console.
- To be able to configure estos ProCall Attendant Console ideally, please look up estos ProCall Attendant Console customize.
- Links to software updates and support can be found on the page Product support.

Help can be accessed any time from the estos ProCall Attendant Console program window via **Help**. Help opens by default on the subject which corresponds to the function just used by you.

In Help the following icons are used:

Icon	Meaning
	Note
	Warning, caution
	Change from earlier versions

2 What estos ProCall Attendant Console is able to offer you

The estos ProCall Attendant Console is a Unified Communications software suite for business. It combines computer-supported telephony (computer telephony integration, CTI) with features for company wide (and beyond company boundaries) online collaboration.

The estos ProCall Attendant Console provides a broad feature set for communication and collaboration with remote call control, conference, presence information, instant messaging, chat and SMS text messaging.

The estos ProCall Attendant Console with its various configuration options adapts perfectly for your personal daily working needs. The estos ProCall Attendant Console integrates well with your favourite applications for e-mail and contact data administration and optimises seamless your workflow and communication processes for business purposes.

Learn more about the essential functions and performance features of estos ProCall Attendant Console here:

2.1 Contact search: Find information about the current contact.

estos ProCall Attendant Console automatically searches in case of an incoming or outgoing call for the appropriate contact information, based on the phone number (particularly the call partner) and displays this information. Which contact data sources are searched and in which order, can be defined in the configuration of the estos ProCall Attendant Console and (by the administrator) in the estos UCServer. If more contacts are found from several data sources for that phone number, the contact data which was last used is displayed as active.

Further you are able to search for the contact data of a person in the search window of estos ProCall Attendant Console by entering a name or parts of it. Then start the call or other activities from the contact detail window.

2.2 ActiveContacts - actively manage contacts

The ActiveContacts technology in estos ProCall Attendant Console shows further information in addition to the contact data and the phone status of the user, e.g., calendar data of Microsoft Outlook®. The information is constantly updated in "real time". Therefore, you are always informed when and how your contacts are accessible. You are able to start and control the communication via a software menu, depending on the available information.

2.3 Presence – see the availability of your contacts

Every user connected to the system owns a status further on referred to as *Presence*. This information is aggregated according to defined rules based on the status of several services: Telephony status (telephony service), calendar status (calendar service), login-log off (system service) and the manually entered status, provided by the user.

The presence shows at any time the current availability of the person you wish to communicate with.

You find an overview of the displayed presence symbols and their meaning under Presence symbols.

2.4 Federation - The trustworthy network

A federation is a secured structure for the communication between members of different organisations (e.g. two companies, company and customer) with the aim to improve cooperation.

Within the federation, presence management permits the exchange of current information about the accessibility/availability of people, even beyond organisation boundaries. So, a suitable method of communication can be selected (e.g. phone, e-mail, chat, etc.).

Within the frame of the federation, every organisation defines which information is revealed and decides which services and systems are used for the exchange of this information.

2.5 **Journal - tracking and planning communication**

The estos UCServer journal informs you about all communication events, e.g. completed phone calls, missed calls and unavailable call participants. The information can be filtered and arranged according to different criteria.

The journal entries can be edited, marked, provided with notes and shared with other users.

All details for future telephone calls can be collected and edited upfront.

This allows you to keep an overview of your entire communications at all times. Important information cannot get lost anymore.

2.6 **Audio/VideoChat - Realtime communication using WebRTC**

The estos ProCall Attendant Console enables an ad-hoc communication with other users via Audio/VideoChat and screen sharing. This is supported within the enterprise network and using federation across enterprise network boundaries.

2.7 **Computer Smartphone Integration via Bluetooth (CSPI)**

The estos ProCall client supports connecting cell phones with the PC using Bluetooth. This connection will make controlling and monitoring of the telephone possible. Furthermore a PC audio device can be used for conversations by cell phone.

2.8 **Softphone - Making phone calls with the PC via a PBX**

The estos ProCall client can be registered via the UCServer at a SIP-PBX. The PC in conjunction with a headset turns to be a VoIP phone.

3 Installation and Base configuration

The installation of the estos ProCall Attendant Console can be done in various ways.

The Base configuration of the estos ProCall Attendant Console is done directly after the successful installation of the software.

3.1 Installation

The installation of the estos ProCall Attendant Console can be done in various ways.

- Requirements
- Manual installation at a workstation by the *.msi* file
- Installation via update service via estos UCServer and the server-side remote installation and update service.
- Installation using group policies in a network domain

3.1.1 Requirements

Requirements for the installation:

Operating system

- Windows® 8.1
 - Windows® 10
 - Windows® 11
 - Windows Server® 2012
 - Windows Server® 2012 R2
 - Windows Server® 2016
 - Windows Server® 2019
 - Windows Server® 2022
- The product manufacturer ensures operation for its software product on operating systems that are still within the support period of the operating system manufacturer.
If the manufacturer support period for your operating system has expired, this also applies to the support for the software product described here, even if this operating system was still supported at the time of the software release.
 - Which operating systems are currently supported can always be found in the release notes for the product.
 - The time for the expiration of support for an operating system version can be found in the release notes.
 - The product manufacturer reserves the right to take operating systems out of support although they are still supported by the operating system manufacturer.
 - An existing software version cannot be run automatically on a future/new operating system.
 - Problems in the software product are only rectified for operating systems for which the operating system manufacturer provides support.
 - Support for the software product is only given for the current last activated product version. This can be acquired at estos Downloads.

Source for the official life cycles defined by Microsoft® for its operating systems:


- Search life cycle for Microsoft® product: Microsoft® Lifecycle Policy

3.1.2 Installation at the workplace

To start the installation at the workplace please double-click the *.msi* file. This starts the Windows® installer leading through the installation procedure. Several configuration options are offered to the user:

Version Information

The exact version number is displayed on the homepage.



If estos ProCall Attendant Console is installed on a 64-bit operating system, a note appears on this page that the 64-bit variant of the TAPI drivers are installed if required.

License

The licence agreement has to be read and accepted by the user before the installation can be continued.


TAPI-driver

The latest version of estos ProCall Attendant Console doesn't require a TAPI driver for communication with the estos UCServer anymore. All functions are provided by direct communication now. This simplifies the installation and maintenance of the software even more in Terminal Server environments. During configuration the following options can be selected:

- Do not install a Tapi driver
- Installation of the client TAPI driver
The client TAPI driver allows third parties the dialing via TAPI. The driver uses estos ProCall Attendant Console as a connection with the estos UCServer to carry out the dialing process. No additional TCP/IP connection is required and the installation and servicing of terminal servers are considerably easier than with TAPI.
- Installation of the enhanced remote TAPI driver
With the help of this driver, third party manufacturer's software can use all functions via TAPI and the estos UCServer. Nevertheless, this driver needs another TSP/IP connection with the server.

Automatic Software Updates

The user may decide here if the estos ProCall Attendant Console should be updated automatically. In this case a local update service is installed to the local Windows® system. The update service stays connected with the central estos UCServer for updating the client software if required.



The related software update service needs to be activated at the central estos UCServer to run the remote software updates successfully.

Connection to the server

Please enter the server here to be connected with the estos ProCall Attendant Console.

The server name or its IP address is entered in the input field when using static configuration. The server can be searched for and selected in the local network with **Search server....** The list displayed contains the following information about the servers found:

Computer name	Computer name of the server
Version	Information about the installed version of the estos UCServer

Method of localization	<p>Broadcast means, that the server has answered a search inquiry on the local network.</p> <p>DNS service record means, that the server was setup in the DNS as a service provider.</p>
------------------------	--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

If a DNS Service Location Record is used for the configuration of the server the estos UCServer should be found and configured automatically.

➔ The setup of a server side DNS Service Location Record is further explained in the help system of the estos UCServer.

Once the target folder for the program installation is entered the software installation completes by installing all files on the system.

Afterwards please start the Base configuration by activating the checkbox and select *finish*.

3.1.3 Installation via update service

The estos ProCall Attendant Console can also be installed on the workstations by the estos UCServer integrated update service.

A Windows® system service will be installed on the workstation executing the installation procedure including the central base configuration loaded from the estos UCServer. The remote installation doesn't require a user intervention. Once finished the Windows® system service supervises the client software version running and starts the update procedure if necessary.

The user is informed about events and the installation progress in a bubble popup at the system tray. A manual intervention of the user is not possible while running remote installations.

The system requirements and the setup of the server based central software installation and update service are described at the help system of the estos UCServer.

3.1.4 Installation using group policies

You can install workstations in the network automatically with the help of the group policy. Proceed as follows:

1. Define which components should be installed on the single workstations. Use the Windows® Installer in administrator mode for this. Start *msiexec/a client.msi*. You can now define a directory in which the prepared installation should be copied.
This need to be an accessible network share. Then select the software components to be installed on the workstations and specify the estos UCServer computer.
2. Start the Active Directory® user and computer management console in which you configure your domain users. Group your users (or computers) in such a way that you have organisational units. You can create group guidelines for each organisation-unit which controls the automatic installation of software.
Open an organisational unit's properties.
Go to Group policy. Add a new group policy.
Open group guidelines with *Edit*.
Add either under *computer configuration - software settings - software installation* or under *user configuration - software settings - software installation* a new package.
Then select the installation package previously prepared via the administrative installation. Read the appropriate documentation on Windows Server®, Active Directory® and group policies.

3.2 Base configuration

The base estos ProCall Attendant Console configuration is carried out, as is appropriate, immediately after the software is installed. The base configuration can also be opened via the Windows® start menu under **estos ProCall Attendant Console My Computer Settings**. The following configuration options are available:

- Language selection of the estos ProCall Attendant Console
- Licenses
- Lines options
- Groupware connection

Basic user settings are configured in **estos ProCall Attendant Console Administration**. In addition to the central configuration, various settings can also be modified directly on a workstation using estos ProCall Attendant Console My Computer settings.



Configuration of certain behaviors or properties will require administrative authorization for estos ProCall Attendant Console. To do this, the user may need to be logged in as an administrator. A button enabling login as administrator will then appear on the corresponding settings page.

3.2.1 ProCall Attendant Console language

By default, estos ProCall Attendant Console is started in the language of the operating system. If this language is not available, estos ProCall Attendant Console is displayed in English.

The language used can be changed in the estos ProCall Attendant Console My Computer settings. Administrators may also specify the language through Active Directory® group policies. If so, the user may no longer change the language.

3.3 Licenses

estos ProCall Attendant Console requires licence keys to operate. Basic properties of estos ProCall Attendant Console are defined by the licence key.

Select license model

At this point there are the following possibilities:

Test 25 licenses free of charge (for 45 days)	An evaluation license is being used. estos ProCall Attendant Console may be tested using all available features for 45 days for up to 25 workstations. At the end of the test period, the licenses must be purchased and entered.
Add license	To enter a new license please use the button " Add ".

List of licenses used

This list shows the licenses entered and its properties.

Property	Description
Description	Description of licenses or its features

Valid until	Displays the license validity period
License	License key (35 digits)

Sum active licenses shows the summary of current valid licenses.

Add

Thereby, new licenses can be added to the list.
 Any number of licenses can be entered.
 The licenses have 35 digits and confirm to the following pattern:
 XXXXXXXX-XXXXXXX-XXXXXXX-XXXXXXX.

Remove

Remove the marked license from the list

Hardware-ID

A hardware ID which is used to create a license bound to the hardware.

3.4 Lines

Here you can select which extensions will be made available in the network.

A line usually corresponds to a phone. All lines available on the computer will be displayed in the list. **TAPI drivers** will provide the lines that should already have been installed on the system.

3.4.1 TAPI-driver

A TAPI-driver for your phone system is required to operate this software.

A TAPI-driver is a system component that is provided by the manufacturer of your telephony device (either free of charge or for a fee).

The TAPI-driver connects the CTI software to the telephony terminal device. Each TAPI-driver supports different functions depending on the implementation. Not all functions which you can perform on the phone itself are always available on the PC.

TAPI-drivers are installed in Settings - Control Panel - **Phone and Modem Options - Advanced**.

Open phone and modem settings:



3.5 Base configuration

The base estos ProCall Attendant Console configuration is carried out, as is appropriate, immediately after the software is installed. The base configuration can also be opened via the Windows® start menu under **estos ProCall Attendant Console My Computer Settings**. The following configuration options are available:

- Language selection of the estos ProCall Attendant Console

- Select estos UCServer
- User log-in information in the estos UCServer
- User settings: general user information
- User settings: contact address and user profile picture
- User settings: telephone numbers
- User settings: services
- Groupware connection
- Exchange Web Services
- Start options

Basic user settings are configured in **estos UCServer Administration**. In addition to the central configuration, various settings can also be modified directly on a workstation using estos ProCall Attendant Console My Computer settings. This way it is possible to fully maintain the workstation settings. If the user got the right from the administrator to configure the workstation settings by himself the user may change the settings anytime.

	The configuration of specific configuration options requires administrative estos UCServer access rights. The user may need to login as administrator in this case. At the related configuration page a login option as administrator appears.
	If you are using a active directory based usermanagement, there are some settings a user cannot change.

3.5.1 ProCall Attendant Console language

By default, estos ProCall Attendant Console is started in the language of the operating system. If this language is not available, estos ProCall Attendant Console is displayed in English.

The language used can be changed in the estos ProCall Attendant Console My Computer settings. Administrators may also specify the language through Active Directory® group policies. If so, the user may no longer change the language.

3.5.2 Connection to the server

The responsible estos UCServer can find estos ProCall Attendant Console through different ways:

- **Static estos UCServer configuration**
With static configuration the host name or the IP address of the estos UCServer is required. Via the button **Search servers...** all estos UCServer available on the network can be displayed. Afterwards select the correct estos UCServer.
- **Use DNS service location record**
By activating option **Use DNS Service Location Record** all necessary information about the Domain Name Service is provided to the Client.

Secure encrypted connection (TLS) is required

This option will force encrypted data transmission between estos UCServer and estos ProCall Attendant Console. A corresponding certificate must be stored on the estos UCServer computer.

Use these settings for all users

estos ProCall Attendant Console supports hosting scenarios in terminal server environments in cooperation with several independent estos UCServer instances.

➔ The Use These Settings for All Users checkbox will only be available on the system-wide server configuration dialog.
 Activate this checkbox if you use *only one* estos UCServer system or all users on this computer (especially for terminal servers) should only use one estos UCServer system. With this option, all users on the computer will be use the system-wide settings.
 If you use several estos UCServer instances and the users of one computer (especially for terminal servers) should connect to different estos UCServer instances, this checkbox should *not* be activated. Thereby, the server connection data will specified explicitly for each user logged in and may be configured optionally from the workstation setup dialog from the Server Configuration for This User tab or from Login Account through estos ProCall Attendant Console.

➔ A user-specific configuration of the server connection data will be taken into consideration by estos ProCall Attendant Console, the SDK components and the advanced remote TAPI driver. In contrast, the automatic updating service and the multiline TSP will always use the system-wide server configuration, regardless of the server configuration for all users.

3.5.3 User authentication

The estos UCServer supports two options for the user authentication:
 Decide either to log-in with your Windows® user name or provide the user name and the password which were configured in the estos UCServer for you.

➔ If users are administered in the estos UCServer, a new user profile can be entered with a *New user* name after authentication as estos UCServer administrator.

3.5.4 User settings: general user information

Here you can enter or update the user's information.



Property	Description
User name (login)	This is the user name for logging onto the estos UCServer service. If Active Directory® is used, this name will be the same as the Windows® login name.
Identity	The user's identity to be clearly identified in the Federation scenario. This identity address ideally corresponds to the e-mail address of the user. Therefore this user is also accessible via the Federation from outside of the company.
First name	The user's first name (e.g. Arthur).
Last name	The user's last name (e.g. Dent).
Displayed name	This is the user's full name (e.g. Arthur Dent). This can occur several times and is only used for display purposes. If the field is empty, a suggestion is automatically shown when the first and last name are entered.

E-mail address	This is the email address of the user. Among other things, it will be used for notifying the user about missed calls and voice-mail messages.
(UC-Password)	The section for changing the password will only be displayed, if the user has been authenticated by estos UCServer itself. If Active Directory® is used, this section will not be displayed.

3.5.5 User settings: contact address and user profile picture

Here you can enter the contact address of the user or update and add a user's profile picture.



Contact address shows all relevant contact details for the user. You may add a contact picture, which will be shown on various places in estos ProCall Attendant Console. This picture will be shown to server users and to federated contacts depending on the given permissions.

	If Active Directory® is used for user management, this information will be displayed for review by the user and cannot be changed.
	The user picture will be scaled free of distortions when added or loaded.

3.5.6 User settings: phone numbers

The user's phone numbers are displayed as provided in his contact data. This refers to the estos UCServer user as well as to Federation contacts. estos UCServer will detect the telephone lines for the phone numbers while loading the user profiles. The user will be assigned the phone lines associated with them automatically without further configuration.

Business phone numbers can be selected from the telephone line list via **Select...**

	User phone numbers and line numbers must be entered in the Supercanonical format in the integrated user administration. Phone numbers from Active Directory® will be shown as entered in the Active Directory®. When user profiles are loaded in estos UCServer, these numbers will be reformatted to supercanonical format.
	If more than one location is used, the phone numbers will have to be stored in supercanonical format in Active Directory®.



Property	Description
Business	The user's primary business phone number
Business 2	Other business phone number for the user
Private	The user's private phone number
Mobile	The user's cellphone number. This phone number is used, for example, to automatically set

	up call forwarding.
Pager	The user's pager phone number. The attribute can be used to store a user's private mobile phone number.
Voice mailbox	Phone number of the user's mailbox. The mailbox is the personal answer machine. This phone number is used, for example, to set up an automatic call diversion.
Recording server	The phone number of an external call recording server. This field is only required if an external server is used and not the integrated call recording server. If this field contains a phone number then this number is used for the phone call recording. Without a phone number, the centrally configured number is used.

Via **Additional Lines...** dialog, you can configure additional lines for users and computers. You can provide the following information from that dialog:

Property	Description
First phone	This is the user's personal phone's internal number. A phone can only have one owner. This assignment is also used for the offline journal.
Second phone	You can specify a second personal phone for the user here.

Phones which stand next to this computer:

Property	Description
First phone	Phone number of the first phone next to the computer
Second phone	Phone number of the second phone next to the computer
	It is possible that some properties will not be displayed if they were deactivated server-side.
	These additional lines for the user and computer will not be listed in the contact details and will not be visible to other users.

3.5.7 User settings: services

Here you can configure or view which estos UCServer services and functions the user may use.

Field	Value
-------	-------

Configure user profile personally	If this option is activated the user is allowed to change server-relevant settings.
Start chat	If this option is activated the user may send text messages to other users.
Allow audio chat	If this option is activated, the user is allowed to use audio chat with other users.
Allow audio/video chats	If this option is set, the user may communicate with other users using Audio- and VideoChat.
Accept screen sharing requests	If this option is activated, the user is allowed to accept screen sharing requests from another user.
Initiate desktop sharing	If this option is activated, the user is allowed share his own screen with other users.
Send SMS	If this option has been activated, the user will be allowed to send SMS text messages.
Send missed calls as an e-mail	Is this option is activated, the user receives an e-mail for every missed call. The user decides in the estos ProCall Attendant Console settings whether to use this option.
Deliver unanswered phone calls as SMS text messages.	If this option is set, the user can receive SMS notifications about missed calls. The user will decide if they want to use this feature when making the estos ProCall Attendant Console settings.
Record calls	If this option is activated, the user may use the function <i>Record calls</i> .
Use phone books	If this option is activated, the user is allowed to use phonebooks as a contact data source.



3.5.8 Groupware connection

Here you can define which product integration is allowed.

- Use estos ProCall Attendant Console with Outlook®**
 The client will connect to an Outlook/Exchange installation if this checkbox is checked MAPI and/or Exchange Web Services (EWS) can connect with Outlook® or Exchange. If Outlook® is used, check the **Use estos ProCall Attendant Console Plug-in with Microsoft Outlook®** checkbox to activate estos ProCall Attendant Console Plug-in for Outlook®. With this

option enabled, an additional toolbar will be added to Outlook®, which provides access to some estos ProCall Attendant Console functions in a context sensitive manner. See Integrating Microsoft® Outlook/Exchange for more information.

- **Connect to Microsoft® Exchange directly**
 estos ProCall Attendant Console can also connect to Exchange Servers directly by using Exchange Web Services. The necessary configuration can be read by estos ProCall Attendant Console from Outlook® directly. All mailboxes configured there will be read and used automatically. Additionally, mailboxes can be added manually by using the 'Configure' button, e.g. when no Outlook® is installed.

	Only Exchange mailboxes from Outlook® can be used automatically, but no POP3 or IMAP mailboxes.
	Exchange Web Services requires .NET Framework v4.0 or newer.

- **Use estos ProCall Attendant Console with IBM Notes®**
 Setting this option permits the client to use the functions and databases of an installed and set-up IBM Notes® Client.
 Depending on the IBM Notes® installation, it may be necessary to manually set the path to the file *notes.ini*. Tick the box before the input line and give the complete path to the file.

Professional applications

Integration with special applications will be offered from this section.

- **Use DATEV with estos ProCall Attendant Console**
 If DATEV Arbeitsplatz Pro has been installed and setup with Telefonie Pro on the computer, integration will be enabled by setting this option. In this case contacts from DATEV databases will be preferred automatically during the initial installation. This can be changed by the user in the database settings.
- **Use Windows® 10 Apps integration**
 On a computer with Windows® 10, it is possible to integrate the included Mail, Calendar, and Contacts apps into estos ProCall Attendant Console. This option will not be shown on older Windows® versions.

3.5.9 Exchange Web Services

Profile Dialog

This dialog shows all configured mailboxes. New mailboxes can be added or removed here and the default mailbox can be selected.

Mailboxes read from Outlook® are grayed out and cannot be deleted.

- **Default mailbox**
 In this mailbox tasks are generated (if desired) and calendar data for creation of the presence status are read out.
- **Use only EWS (disable MAPI)**
 Can be used to disable the MAPI interface. If the box is not checked, MAPI as well as EWS are used simultaneously.
- **Monitor Outlook® Inbox with EWS**
 With this setting, estos ProCall Attendant Console monitors the Inbox of the default mailbox and displays unread emails.

Dialog: Add mailbox

estos ProCall Attendant Console can log on to an Exchange server either by Windows® login or by username and password.

The URL of the server needed to connect to Exchange Web Services is usually detected automatically and you only need to enter your e-mail address in this dialog.

- **E-mail address**
The email address of the mailbox to be added.
- **Server-URL**
The address of the server through which the Exchange Web Service can be reached.
This is usually in the form "https://yourserver.domain/EWS/Exchange.asmx".
- **Automatically detect server URL**
This URL is usually recognized automatically by estos ProCall Attendant Console.
If this is not possible, the automatic detection can be deactivated here and the server URL can be entered directly.
- **Use Windows® login**
If it is possible to authenticate against the Exchange Server using the domain, this option should be set.
Otherwise estos ProCall Attendant Console asks for username and password.

3.5.10 Start options

Here you can define, when the estos ProCall Attendant Console will be started.

Start estos ProCall Attendant Console with Windows® logon.

If this option is selected, estos ProCall Attendant Console will start when the user logs on to the computer. This option can also be changed in the settings of the program itself.

Start estos ProCall Attendant Console now

With this option, estos ProCall Attendant Console will start for initial use immediately after installation has completed.

4 Usage of existing contact data

Contact data from other programs can be implemented or searched for. estos ProCall Attendant Console functions can be used from Microsoft Outlook® and Microsoft® Exchange. More information about supported contact data sources can be found on the following pages.

- Supported data sources
- Data from IBM Notes® (was: Lotus® Notes)
- Cooperation with Microsoft® Outlook/Exchange
- Google integration

4.1 Supported data sources

Contact data source integration is an integral part of estos ProCall Attendant Console. Based on contact data, estos ProCall Attendant Console offers you an extensive catalogue of functions which ideally support you in your work.

In estos ProCall Attendant Console numerous contact data sources can be linked:

- **estos ProCall Attendant Console User**
This estos UCServer provided data source gives you access to all user, who are using estos ProCall Attendant Console on the same estos UCServer along with you. As a rule, these are your work colleagues who also use estos ProCall Attendant Console.
- **Lines**
This data source is also managed by estos UCServer by your administrator and gives you access to all available phone lines in your phone system.
- **estos ProCall Attendant Console Favorites**
The data source Favorites gives you quick access to all the contacts you have stored in your favorites.
- **Outlook®**
With estos ProCall Attendant Console, you can use all contact data stored in your Outlook® client. Thereby, you may choose to only use individual contact folders or all contact folders for an Outlook® inbox. You can also choose to include public contact folders, if your Exchange system provides them and you have access to them.
- **Exchange Web Services**
In addition to Outlook®, data can also be used directly from an Exchange server through its web service (as of Exchange Server 2007). Office 365 can also be integrated using this option, naturally.
- **IBM Notes®**
You can use all IBM Notes® (= formerly Lotus® Notes) address books in estos ProCall Attendant Console. Both the local address book and address books on a Domino server can be directly connected and contacts stored in them can be used.
- **LDAP data sources**
With the option of connecting LDAP data sources estos ProCall Attendant Console makes a powerful interface available for accessing various contact data stocks provided they offer an LDAP interface themselves.
- **estos MetaDirectory**
As a special case of a LDAP data source the estos MetaDirectory can be integrated in estos ProCall Attendant Console. Via this path you can integrate data sources such as IBM Notes®, Tobit David Infocenter (in version 3.5 or earlier) or ordinary ODBC data sources in estos ProCall Attendant Console. Further information can be found in the estos MetaDirectory help file.
- **Phone books**
estos ProCall Attendant Console permits the integration of phone books. At the moment, data from "Das Telefonbuch Deutschland" as well as "TwixTel Switzerland" can be directly accessed from estos ProCall Attendant Console. You can also use KlickTel Server in connection with estos MetaDirectory.

Information about the integration, configuration and use of contact data sources can be found under data sources.

4.2 Data from IBM Notes®

IBM Notes® address books can be integrated into estos ProCall Attendant Console as contact data sources. Apart from local address books, address books on a IBM® Domino server can also be used.

The integration allows contacts to be edited and opened directly in IBM Notes® from within estos ProCall Attendant Console. New contacts can equally be created in IBM Notes® via estos ProCall Attendant Console. Please bear in mind, however, that the functions for editing and creating contacts are only available if IBM Notes® is running.

Dialing phone numbers from within IBM Notes® using estos ProCall Attendant Console can be realized with scripts.



If a password is required for access to a IBM Notes® address book this must be entered when estos ProCall Attendant Console is started. Optionally, the password can also be saved in estos ProCall Attendant Console.

Information about the integration, configuration and use of contact data sources can be found under data sources.

4.3 Cooperation with Microsoft® Outlook/Exchange

estos ProCall Attendant Console works closely with Microsoft Outlook®. This cooperation is based on two components:

- **Joint data usage**
 estos ProCall Attendant Console uses the MAPI interface for accessing information from Outlook® or providing new information to Outlook®.
 Alternatively, an Exchange Server can be integrated directly by using Exchange Web Services.
- **Outlook® user interface toolbar**
 In order to be able to use estos ProCall Attendant Console functions from Outlook®, a COM add-in can be installed upon request, which will add a toolbar to the Outlook® user interface for quick access.

4.3.1 Joint data usage

Contacts

Contact information from the Outlook/Exchange database can be sought and displayed by estos ProCall Attendant Console.

Contacts from other data sources can be comfortably created in the Outlook/Exchange database via estos ProCall Attendant Console so that they are also available there.

E-mail

If desired, the client will display the number of new emails in the inbox.

Calendar

estos ProCall Attendant Console can use Outlook/Exchange calendar information to determine the user's presence status. The user can define whether private appointments should be included and also prevent access to this information.

Tasks

The Outlook/Exchange task database can be used for comfortable call scheduling in estos ProCall Attendant Console.

Journal

The Outlook/Exchange journal can be used to save a call journal created by estos ProCall Attendant Console. Copies of the estos UCServer journal entries are made for this purpose in this journal either by mouse click or automatically. It is also possible to define under which conditions such an entry should be copied.

Exchange Web Services

Should Exchange Server have been integrated directly through Exchange Web Services, estos ProCall Attendant Console will also be able to read the necessary configuration directly from Outlook®. All mailboxes setup there will be checked and used automatically.

4.3.2 estos ProCall Attendant Console Plug-in for Outlook®

To make context-sensitive access to estos ProCall Attendant Console features directly from Microsoft Outlook®, installation will add a plug-in-toolbar to Outlook®. Making calls, searching for contacts and creating tasks will be made possible by this plug-in.



Installation

The toolbar is set up as part of the estos ProCall Attendant Console installation.

Functions

The toolbar consists of three buttons and one input field:

Element	Description
Phone call	<p>A menu with different functions is displayed by clicking on this icon. The functions are based on the displayed or selected elements.</p> <ul style="list-style-type: none"> • E-mail Search for sender and sender's e-mail address. • Contact Menu for direct dialing of all the contact's phone numbers. • Task If the theme of the dialed or displayed task contains a phone number in square brackets ([]) a menu entry for directly dialing the number is created. • Other element All other elements have an entry in this menu to open the client focussing on the search line. <p>All elements always have the redialing list as last menu entry.</p>
Search field	<p>With the help of this entry field the estos ProCall Attendant Console can be prompted to search for a term or dial the entered phone number. Enter appropriate text or phone number and confirm it with the enter key.</p>
Plan call	<p>A call can be schedule for contact using this feature. To do so, a new task will be created using a specially formulated subject.</p>
Info	<p>estos ProCall Attendant Console will display an informational window about this contact, which will list special information about the calls (done, scheduled and unanswered) in addition to contact data.</p>

	The buttons <i>Plan call</i> and <i>Info</i> are only available if there is a contact selected.
	Presence status will only be displayed for contacts found in the list of favorites.

4.4 Google integration



estos ProCall Attendant Console is able to use contacts and appointments from your Google account. To enable Google integration, your system administrator has to allow and configure this feature. As soon as your administrator has done this, estos ProCall Attendant Console will ask for the necessary permissions through your browser.

Contacts

All contacts from your Gmail account will be used.

Appointments

By default, only appointments from your primary calendar will be used. If more calendars should be included, you can configure this under Integration -> Calendar. You can integrate as many calendars as you want, including shared ones from other users.

	By default, Google flags appointments as private.
	Due to technical limitations, updates from Google to estos ProCall Attendant Console may take a few minutes.

5 Work with estos ProCall Attendant Console

You can find out how to use estos ProCall Attendant Console for your tasks from here. Please choose a subject.

- Program start and overview
- Manage contacts
- Use presence information
- Plan communication
- Communicate

5.1 Program start and overview

You can find out how to start or stop estos ProCall Attendant Console and become familiar with the programs' user interface from here. Please choose a subject.

- estos ProCall Attendant Console start and shut down
- Login account
- Main window
- Menu bar icon
- Speech bubble info

5.1.1 estos ProCall Attendant Console start and shut down

Start

It was already specified in the Base configuration (Start options) whether estos ProCall Attendant Console should automatically start with the Windows® login. You can also configure this at a later time via the estos ProCall Attendant Console My Computer settings in the Windows® start menu.

estos ProCall Attendant Console can be started manually at any time by the Windows®-start menu.

Exit

estos ProCall Attendant Console will be closed by **Close** item on the main menu or the corresponding entry on the context menu for the tray icon.

5.1.2 Login account

In the dialog "login account" the user account can be configured in order to log onto the estos UCServer.

5.1.2.1 *Configure UCServer*

If the server configuration was not specified for all users during the estos ProCall Attendant Console installation or via the group guidelines, the estos UCServer can be changed (which the estos ProCall Attendant Console connects to) via the dialog "Login account".

Configure automatically

If the system administrator configured a DNS Service Location Record for the estos UCServer, the estos UCServer can be automatically located and configured.

Find server

All available estos UCServer's in the network can be localized and placed into the input field for the server name with the dialog "Search server".

5.1.2.2 Configure User account

Enter here the user name and the corresponding password to log on to the estos UCServer.


Use Windows® login

If the system administrator activated the estos UCServer authentication via the Windows® domain, it is alternatively possible to use the Windows® login.

5.1.3 Main window

The main window of estos ProCall Attendant Console gives you access to the functions supporting your everyday work.

The significant sections of the main window will be described by the following material.



[1] My own presence

[2] Log in and out of agent/call groups (optional)

[3] Search input

[4] Tabs for contact search, favorites, journal , missed and planned calls

5.1.3.1 My presence






The **My Presence** section shows you the most important information about your presence, the status of your phone lines and audio/video devices, and your upcoming appointments. In addition to seeing this information,

you can go to this section to change your presence state, configure call forwarding settings and access your calendar. You'll find more detailed information on the **My Presence** section at Your own presence.

5.1.3.2 Main menu

The main menu can be opened with the main menu button ▼ which is situated in the top right corner.

It has features which will support you in your daily routine or with which you can adjust estos ProCall Attendant Console to your personal needs.

-  **Journal browser**
This menu item will open the Journal Browser. In contrast with the Journal Tab on the main window, you will be able to track all available journal entries.
-  **Inbox**
This entry opens Outlook® to show you your inbox.
- **Display on incoming call (own line)**
Activate this option in the **Characteristics** sub-menu if the main window is to be displayed for incoming calls. This option is available only if the main window is docked to the edge of the screen.
- **Display on incoming call (all lines)**
Activate this option in the **Characteristics** sub-menu if the main window is to be displayed when a call comes in from a saved contact (or line). This option is available only if the main window is docked to the edge of the screen.
- **Docked to the edge**
Set this setting in the **Views** sub-menu if the main window is to be docked at the edge of the screen as a sidebar. You can also place the main window next to a different screen edge by picking it up and dragging it to the appropriate position.
- **Always on top**
Set this setting in the **View** sub-menu if the main window is always to be displayed. It can then no longer be covered by other windows.
- **Hide not logged in users**
Configure this setting in the **View** sub-menu if you don't want to display all users in Favorites or all other contact groups. This will cause only users who are logged in to be visible. In spite of this, all contacts who do not have a presence address as well as all function keys will always remain visible.
- **Group by grouping attributes**
If this setting is activated in the **View** sub-menu, contact groups are displayed for all grouping attributes used and contacts are sorted according to the grouping attributes which they set for themselves. In this case, all contact groups which were created by administrators or created manually, as well as the contact group in Favorites, are hidden. Users or contacts who do not have a grouping attribute set are displayed in the "Other contacts" group. Function keys appear in the "Keys" group. You can specify the grouping attribute which applies for you in the menu with presence settings and presence profiles, under the item Set grouping attribute.
- **Display group title bar**
Activate this option in the **View** sub-menu if you want group title bars to always be visible. If contact groups or other tabs are arranged one above the other ("docked"), the title bars will always be visible regardless of this setting.
- **Group title bar position**
Use this option in the **View** sub-menu to specify the position of tab title bars. You can choose for title bars to be placed at the top, bottom, left or right.
-  **Settings**
Click here to open the Settings. Here you can define or change the most important estos ProCall Attendant Console settings.
-  **Help**
Opens this online help
-  **About ProCall Attendant Console**
Here you get information about the product version of estos ProCall Attendant Console and you have the possibility to get more detailed support informations and log files.

-  **Exit**
Ends estos ProCall Attendant Console.

5.1.3.3 **Agent and call groups**

If the telephone system and estos ProCall Attendant Console are configured to use agent or call groups with login/logout function, the groups in which you are a member are displayed. You can log in and out of the groups and (if it is supported) start and stop post-processing.

5.1.3.4 **Search input line**

You can use the search input at any time to quickly find your contacts or to simply dial a number. You can immediately re-use the contacts found in the Search tab or save them in the Favourites tab for later use.

5.1.3.5 **Tabs**

The following tabs can be put in the foreground:



- **Contact search**
Lists the hits for a contact search
- **Favorites**
Space for your most important contacts and speed-dial keys
- **Journal**
Collects the last calls made and received
- **Planned**
Saves the planned calls

5.1.4 **Menu bar icon**






The symbol in the notification area always gives you a fast access to the estos ProCall Attendant Console main windows. Just left click on the symbol.

During a call, you can always move the Conversation Window into the foreground. If a conversation window is not open or all conversation windows have been displayed, the main window will be shown. Furthermore, your current Presence Status will be shown on the tray icon.

In contrast, if you right-click on the tray icon, you will have access to the following features from the context menu:

- **Presence Profile**
The Presence Profiles menu will display all configured presence profiles and allow quick changes to your own presence. In addition, a presence status that was potentially changed manually can be reset using the Restore Status option. For more information, see Your Own Presence.
-  **Journal browser**
You can open the Journal browser with this menu item. Unlike the Journal tab in the main window you can consult all available journal entries here.
-  **Inbox**
The Inbox function switches to Outlook®. You can thus keep an overview of your e-mails received.
- **Display on incoming call (own line)**
Activate this option in the **Characteristics** sub-menu if the main window is to be displayed for incoming calls. This option is available only if the main window is docked to the edge of the screen.
- **Display on incoming call (all lines)**
Activate this option in the **Characteristics** sub-menu if the main window is to be displayed when a call

comes in from a saved contact (or line). This option is available only if the main window is docked to the edge of the screen.

- **Docked to the edge**
Set this setting in the **Views** sub-menu if the main window is to be docked at the edge of the screen as a sidebar. You can also place the main window next to a different screen edge by picking it up and dragging it to the appropriate position.
- **Always on top**
Set this setting in the **View** sub-menu if the main window is always to be displayed. It can then no longer be covered by other windows.
- **Hide not logged in users**
Configure this setting in the **View** sub-menu if you don't want to display all users in Favorites or all other contact groups. This will cause only users who are logged in to be visible. In spite of this, all contacts who do not have a presence address as well as all function keys will always remain visible.
- **Group by grouping attributes**
If this setting is activated in the **View** sub-menu, contact groups are displayed for all grouping attributes used and contacts are sorted according to the grouping attributes which they set for themselves. In this case, all contact groups which were created by administrators or created manually, as well as the contact group in Favorites, are hidden. Users or contacts who do not have a grouping attribute set are displayed in the "Other contacts" group. Function keys appear in the "Keys" group. You can specify the grouping attribute which applies for you in the menu with presence settings and presence profiles, under the item Set grouping attribute.
- **Display group title bar**
Activate this option in the **View** sub-menu if you want group title bars to always be visible. If contact groups or other tabs are arranged one above the other ("docked"), the title bars will always be visible regardless of this setting.
- **Group title bar position**
Use this option in the **View** sub-menu to specify the position of tab title bars. You can choose for title bars to be placed at the top, bottom, left or right.
-  **Settings**
Open the estos ProCall Attendant Console with Settings in which you can adapt estos ProCall Attendant Console to your requirements.
-  **Login account**
The dialog "Login account" let you inspect the current server connection or log in to estos UCServer under a different user account.
-  **Help**
Opens this online help
-  **About ProCall Attendant Console**
Here you get information about the product version of estos ProCall Attendant Console and you have the possibility to get more detailed support informations and log files.
-  **Exit**
Exit estos ProCall Attendant Console

5.1.5 Speech bubble info

The speech bubble info window is a small information window at the bottom edge of the screen, which shows you any missed calls, new email messages, new chats and scheduled calls, for example.

If you have missed a call or received a new email, for example, the info dialog will be always displayed. Thus, you will immediately be able to see all of the important information at a glance. You can also change to the relevant view immediately if you click on the desired field:

Field	Function
E-mails	Click the e-mail field to open Outlook's Inbox and view your new e-mails.

Planned	Click the field with the planned calls to display the main window with the Call planning. You will find all planned calls here.
Challenge-Response	Click on the row with new authorization requests to display a dialog with the list of authorization requests which are currently pending. You will see all pending authorization requests here.
Fax messages	Click on the row with new fax messages to display the new fax messages which have come into the inbox. You will see all new fax messages here.

You can also close the informational speech bubble window either by clicking on the Close icon at the top left of the window or by deactivating the corresponding option on the Behavior tab on the Settings dialog.

5.2 Manage contacts


Here you can find out how to find contact details for a person in your database and how to organize this data. Please, choose a subject:

- Search contacts
- Contact details
- Telephone number formats
- Authorizations
- Favorites
- ActiveContacts
- The Phone-Link

5.2.1 Search contacts

5.2.1.1 Search with input line

The connected data sources are browsed via the search input line. The contacts found will appear on the **Search** tab and can be immediately used for your work or, for example, dragged to the Favorites list for later use.



[1] Data source selection

[2] Search input

[3] Extended search / last search terms

You can use the search input with four different search variants:

- **Name search**
The name search is the default search case. All contacts with the specified search term in the **last name, first name, company name** and **display name fields** (insofar as they exist) are sought. For some data sources, such as Outlook® or Exchange Web Services, additional entries for name searches can be indicated using the Datasources tab.
- **Phone number search**
A phone number search instead of a name search is started as soon as you enter a search term in the search input field which estos ProCall Attendant Console can interpret as dialable. All contacts are found who have the searched phone number in a phone number field.

- **Search by e-mail address**
A search across all e-mail fields is started if estos ProCall Attendant Console recognises the search term as an e-mail address. All contacts are found who have the specified e-mail address.
- **Detail search**
With help of the detail search you can search for terms in dedicated fields. For example you can search for all contacts with name "estos" in the city "Starnberg".

The detail search uses a syntax where all search terms are separated by comma. The position of the term in the line of commas determines the field where this term is search for.

Default order of the fields is *Name,First name,Company,Zip code,City,Street,Phone number*. The Fields can be configured in the settings at Search parameters.

Detail search example

- You are searching for the contact "Anna Meier". Enter the last name in the first position and the first name in the second position. The search entry is "Meier, Anna".
- You are searching for contact "Anna Meier". The town and the postcode are in fourth position. The company name is left empty as this is not known. The search input therefore reads "Meier, Anna,Starnberg".
- You can also use the postcode (Starnberg's postcode is "82319"). The search input then reads "Meier, Anna,, 82319" or "Meier, Anna,, 82319 Starnberg".
- You are looking for contact "Meier" in "Munich Street". The street is in fifth position. The town is not known and is therefore left empty this time. The search input reads "Meier,,,,Munich". Please note that, as with all other search terms, the street name does not have to be written out in full.
- You are looking for contact "Meier" with the phone number "08151123456" (Germany). The search input for this reads "Meier,,,,,08151123456".

- **Advanced search entry**
The advanced search is started via the arrow symbol at the end of the search line. It is helpful for users who do not want to use the comma syntax while searching. When entering the search criteria the appropriate comma syntax is entered automatically in the search field.

5.2.1.2 Search tab

The search results are received on the **Search** tab if a new search has been started by entering the search criteria in the search field.

All available functions for the selected contact are displayed in the context menu. The contact menu appears if you click a contact with the right mouse button. Alternatively you can also press the context menu button or the Enter key on the contact.

Some functions which can be used on contacts will be highlighted as links on the shown contact. So if you want to call the contact, just move your mouse over the phone number and left click it. The following table lists all such available functions.

Type	Description
Display name	Opens the Contact details for the contact. Alternatively, you can open the contact with a double click.

	<p>Press the CTRL key at the same time (when possible) to open and edit the contact.</p> <p>If the current contact was automatically generated because a contact matching the search criteria was not found, that contact may be saved in Outlook® using this link, by double clicking in Outlook® or through Exchange Web Services.</p>
Address field	<p>Opens the Web browser and displays the address on the map.</p> <p>When pressing the CTRL key at the same time a route to the contact is found.</p>
Phone number	<p>Dials the number on the phone and sets up a call to the subscriber.</p> <p>If you press the CTRL key down while you click on the phone number, the phone call is prepared. Press the CTRL key at the same time as the Shift key, while you click on the phone number, and the phone call is planned.</p>
E-mail address	<p>Opens the e-mail editor and enters the e-mail address as the recipient.</p>
Presence identity (e.g. SIP-URI)	<p>Start a new chat with the contact with presence identity.</p>
Website	<p>Opens the Web browser with the Internet address which was stored in the contact.</p>
Data source (or data source icon)	<p>Opens the contact folder storing the contact. Please note that this feature will only be available for Outlook® and Exchange contacts.</p>

The presence symbol gives you the actual presence state of the found person. You can get all available presence informations about this contact in the tooltip by moving the mouse cursor over this presence symbol.

The search result list can be alternatively arranged with data source, display name, surname or company . The grouping lines can be shown or hidden. Settings can be changed in the context menu which can be accessed by a right click on the row header.

The contacts found can be sorted in ascending (A-Z) or descending (Z-A) order. Click to change the sequence on the column header where it is displayed.

The results list allows the selection of several contacts. Keep the CONTROL key pressed while selecting individual contacts with the mouse. These selected contacts can be dragged into the register card **Favorites** or functions may be carried out that are available for all contacts. That way, for example, you can write an e-mail to several recipients. So it is possible to write emails with more than one recipients for example.

The search result list also allows the selection and copying of single contact fields for the chosen contact. If it contains a action link, move the mouse cursor over the appropriate contact field or a little bit to the left or right beside it. As soon as the mouse cursor changes and indicates a text choice, you can select by holding down the mouse key and pulling the contact fields.

estos ProCall Attendant Console supports two different views in the results list

1. Only the details of the last selected contact will be displayed by default. All other contacts will only show with the most important entries, such as like Name, Company,, Presence and Data Source.
2. Alternatively, you can also display the contact details in the lower area of the search list. For this, pull the divider at the lower edge of the search list upwards with the mouse. You can remove the contact details area again by arranging the divider at the lower edge of the window. You can also move the divider with the CTRL+G key combination. Now use the arrow keys to change the new size of the detail area upwards or downwards. You confirm your input with the Enter key and cancel it with the ESC key.

























The indicated contact fields and the click actions on the contact fields can be individually adapted in the settings under Search result.

5.2.2 Contact details

The contact details window contains all available informations and functions for the contact in question. You may open it with the entry **Open contact details...** in the context menu of the contact or by double click on the contact.

All functions available for the contact are to be found in the icon bar at the upper edge of the window:

-  **Make call**
You can dial every phone number of a contact. The numbers are categorized with symbols:
 -  **Business phone number**
 -  **Mobile phone number**
 -  **Services - software**
 -  **Further phone numbers**
-  **Plan call**
Use this function if you want to call the contact later. Planned calls will be restored at estos ProCall Attendant Console after a restart of the client.
-  **Prepare call**
This function permits you to prepare a call. Prepared calls are created directly before a call and permit you to select special parameters such as project parameters etc. before the call is connected.
-  **Start a Chat with the contact.**
This function allows you to start a text based chat.
-  **Start an AudioChat with the contact.**
Start an AudioChat with the contact. The icon is inactive or grey if the related contact doesn't offer the feature, if no Audio devices are available or if the feature is deactivated.
-  **Start a VideoChat with the contact.**
Start a VideoChat with the contact. The icon is inactive or grey if the related contact doesn't offer the feature, if no Video and Audio devices are available or if the feature is deactivated.
-  **Share screen**
Pressing the Share Screen button will allow a local screen to be shared with a remote contact, if the rights have been granted by the administrator.
-  **Request Screen Sharing**
Would you like to see another user's screen, you can also request to share the screen by clicking Request Screen Sharing. The feature is available only if the related rights are granted by the administrator.
-  **Edit contact**
With this function you can open and make changes to the original contact. For example, the Outlook® contact editor is opened for an Outlook® contact. Please note that this function is only available if the contact comes from Outlook® or IBM Notes® and the application associated with the contact is installed on your computer.
Exchange Web Services contacts may be edited using either the installed copy of Outlook® or the Outlook® Web app.

-  **Create new contact**
Click here if you wish to use the existing contact as a template for a new contact. A typical application is a further contact person in the company.
-  **Open calendar**
With the help of this function you can display the opened contact's calendar. Please note that this function is only available for estos ProCall Attendant Console users who are configured on your Exchange system and that the subscriber's calendar must be enabled.
-  **Contact folder**
Select this entry to open the contact folder where the contact has been stored. Note that this feature will only be available if the contact originated from Outlook® or Exchange Web Services.
-  **New Outlook® journal entry**
Click here to create a new journal entry in Outlook® or on Exchange Server for this contact. Note that estos ProCall Attendant Console no longer be able to open this contact afterwards.
-  **E-mail**
If you have stored an e-mail address for the contact this function opens the e-mail editor with the recipient's address already filled in.
-  **Website**
If you have specified a Web site for the contact this function opens the browser and loads the relevant Web site.
-  **Clipboard**
This function copies all contact detail information to the clipboard. This information can thus also be used in other applications.
-  **Map**
Call up this function to show the location of the contact on a map in the web browser. The map service set in estos ProCall Attendant Console is used. Please note that there must be a complete address set up in the contact for this function.>
-  **Route**
Call this function to display a route to the contact's location in the Web browser. The map service set up in estos ProCall Attendant Console is used for this. Please note that you must have configured your own address in the Location settings. The contact must also have an address.

5.2.2.1 Overview tab

The tab **Overview** will show all informations about a contact which were stored. Here you can see all phone numbers, all addresses or the note for example.

Some entries are clickable like links. So you can just click on a phone number to call the contact for example, or send an email by clicking on the email address.

The tab **Overview** is generated using the template file *contact.xslt*, which can be adopted to your needs. For more information about adopting it see Dialog adaptation with Templates.

5.2.2.2 Journal tab

In the **Journal** tab all phone calls made with a contact can be found.

This impersonated journal is mostly the same view as in the tab Journal in the main window.

5.2.2.3 Planned tab

The **Planned** tab contains all planned calls you have stored for the opened contact. This impersonated view is the same as the Planned tab in the main window according to all other functions.

5.2.3 Telephone number formats

5.2.3.1 Supercanonical number

... makes it possible to distinctively indentify a caller. estos UCServer and estos ProCall Attendant Console do exclusive use this format internally for all phone numbers. For display the numbers can view reformated in a

beautified form. Phone actions will be performed with the shortened version.

Supercanonical phone numbers are starting always with a '+' character and have the following format:

+Country Area Number.

No whitespace characters are used. The number consists only of numerics and the '+' character.

Example: +4901234567

5.2.3.2 Service numbers

... are official phone number which cannot be given in an international format. For example the german emergency number (110) or the directory assistance (118xx). To dial such numbers with the PC, they have to be longer than the internal numbers or they have to be configured as a rule for external numbers. These numbers will be given directly as dialable without any whitespaces.

Example: 11833

5.2.3.3 Phone number

Phone number	Description
Dialable phone numbers	<p>... will be stored in exactly the format wich is needed to dial it on the PBX. This numbers may be reformatted with the rules stored in the estos UCServer if needed.</p> <p>Examples:</p> <ul style="list-style-type: none"> • Phone number internal extension number • Phone number external dialing code Number of subscriber 12345 in the local area network • External dialing code Country Area code Phone number Number of a subscriber in a different country
Phone numbers for display	<p>... will be used by estos ProCall Attendant Console, if this format can be generated with country codes and city codes available.</p> <p>+Country (area code) number</p> <p>Example:</p> <p>+49 (30) 123456 Phone number of subscriber 123456 in Berlin, Germany</p>



The examples above are valid for germany and are strongly related to the according country. In the location settings you can see, which dial rules are valid for your location.

5.2.4 Authorizations

The display of information on a contact in Favorites or in other contact groups is dependent on *authorizations*. Additionally to the visibility the authorizations defines the availability of contact related functions which are accessible for the user throu the *ActiveContacts*

5.2.4.1 Granting authorizations

Each user can give other users or contact, who are connected to the system via federation, authorizations on the own contact or phone lines. These authorizations are strongly additive to already given administrative rights. You cannot remove already given rights.

Authorizations can be assigned via the ActiveContacts context menu (in Favorites or in other contact groups), under the menu item **Customize authorizations**.

Authorizations apply to contact data of the user and to dynamic informations and functions, which are provided by the estos UCServer. The authorizations on the contact have a fixed definition.

5.2.4.2 Authorization inquiry dialog

If a user adds a contact to his or her Favorites or into a different contact group but was not yet granted permission to do so, the newly added contact will receive a corresponding authorization request.

The dialog shows a list with the current authorization inquiries. Every line contains the name and/or the identity of the contact requesting authorization. One or several contacts can be selected from the list.

Below the list is a drop down menu where the authorization level can be selected. The authorizations are applied for the selected contacts via a click on **Apply**. These contacts are then immediately placed in the first contact group in Favorites on the main window.

It can be determined that selected contacts will receive no presence information with **Reject**. This corresponds to the authorization level "Blocked". This definition is applied immediately but the contacts do not appear in Favorites.

If a contact that has been locked, should have more permissions, so you have to "Add Contact ..." to the favorite with his identity first.

The allocation of authorizations can also be carried out via the context menu which can be displayed by right clicking on contacts.

Close closes the authorization allocations dialog.

5.2.4.3 Change authorization levels

The Favorites will be able to view and change the authorizations once granted by simply using the context menu under **Authorization Level**.

5.2.4.4 Remove authorizations

To revoke authorizations from a contact, this is also done in the context menu with the option **Blocked**. Thereby the contact receives no status updates or other information like names or e-mail addresses.

If a contact is completely deleted from all contact groups (e.g. Favorites), the contact can be set to *blocked*. If this is not what you want, the authorization level will be completely reset, so that this contact can start a new authorization request.

5.2.4.5 Table of user and contact authorizations

The authorizations which can be given to other users are differentiated in 5 levels:

- **Blocked:**
Blocked contacts see only your name and your e-mail address and no further information about yourself.
- **Public:**
Public contacts see your name, job title, company, business telephone numbers, cell phone number, and e-mail address.

- **Business:**
Business contacts will see certain contact information and also restricted information about your availability.
- **Team:**
Team colleagues see detailed contact information and differentiated presence information including notes.
- **Personal:**
Personal contacts see detailed contact- and presence information, inclusive a note and private data.

The overview displays by which authorization level what contact data is transmitted to other users:

Information	Blocked	Public	Business	Team	Personal
Contact picture		X	X	X	X
Display name	X	X	X	X	X
Job title/position		X	X	X	X
Company		X	X	X	X
Department (Active Directory® only)			X	X	X
Office			X	X	X
Business address			X	X	X
Work phone		X	X	X	X
Business telephone 2		X	X	X	X
Mobile number		X	X	X	X
Pager			X	X	X
Private phone					X
additional phone numbers (Active Directory® only)					X
Business fax number			X	X	X
E-mail address	X	X	X	X	X
SIP address		X	X	X	X
SharePoint/Webseite			X	X	X

- ➔ The permission levels restrict only the contact data exchanged via presence information, i.e. primarily presence information transmitted via Federation. The permission level does not affect the contact search. Contact data, such as the mobile phone number, is still visible via a contact search, regardless of the permission levels.
- ➔ X* In these authorization levels the notice will only be transmitted unrestricted within the users of UCServer. Contacts via Federation receive the notice only if at least the authorization level **Team member** is allowed in the domain authorizations.

In estos UCServer further information and functions are available to give authorizations to a contact. The following definition is valid for standard authorization levels:


Authorization	Description	Blocked	Public	Business	Team	Personal
View contact picture	A contact image stored for the user is visible		X	X	X	X
See presence	The other user is allowed to see the presence (Present, Absent...).		X	X	X	X
Set presence	The other user is allowed to change the presence. This right should be set only in the case of special positions of trust.				X	X
See note	The other user is allowed to see the note.		X	X	X	X
Set note	The other user may enter a note.				X	X
See private appointments	The other user is allowed to see the appointments marked as private from the calendar, if the user has released his appointments. This right should			x with the note "Private"	x with the note "Private"	X with subject and place

		be set only in the case of special positions of trust.					
See public appointments		The other user is allowed to see the appointments marked as public from the calendar, if the user has released his appointments.			X	X	X
Phone:							
See existing phone numbers		The phone numbers assigned to the user (phone number/extension of all lines) are displayed when the mouse pointer is moved to the presence display.		X*	X*	X	X
See line status (free/busy)		The other user can see if the phone line is free or busy			X*	X	X
First line (Business 1)	See outgoing numbers	The other user is allowed to see who the user is calling with his primary phone. This right should be set only in the case of special positions of trust.			X*	X	X
	See incoming phone numbers	The other user is allowed to see who the user is currently being called by on their primary phone.			X*	X	X
	See diversions	The other user is allowed to see that		X*	X*	X	X

		call forwarding is enabled on the phone.					
	See the number of a set call forwarding	The other user may see to which destination number call forwarding is activated on the phone. This right should be set only in the case of special positions of trust.			X*	X	X
	set Call forwarding	The other user is allowed to set up call forwarding on the line.					X
	Pickup call	The other user is allowed to pick up incoming calls on the first line.				X	X
Second line (Business 2)	See outgoing numbers	The other user is allowed to see with which caller the user is calling with his second phone. This right should be set only in the case of special positions of trust.				X	X
	See incoming phone numbers	The other user is allowed to see who the user with his second phone is currently being called by.				X	X
	See diversions	The other user is allowed to see that call forwarding is enabled on the phone.		X*	X*	X	X



	See the number of a set call forwarding	The other user may see to which destination number call forwarding is activated on the phone. This right should be set only in the case of special positions of trust.				X	X
	set Call forwarding	The other user is allowed to set up call forwarding on the line.					X
	Pickup call	The other user is allowed to pick up incoming calls on the second line.					X
additional lines	See outgoing numbers	The other user is allowed to see which dialog partner the user is calling. This right should be set only in the case of special positions of trust.				X	X
	See incoming phone numbers	The other user is allowed to see who the user is being called by.				X	X
	See diversions	The other user is allowed to see that call forwarding is enabled on the phone.		X*	X*	X	X
	See the number of a set call forwarding	The other user may see to which destination number call forwarding is				X	X

		activated on the phone. This right should be set only in the case of special positions of trust.					
	set Call forwarding	The other user is allowed to set up call forwarding on the line.					
	Pickup call	The other user is allowed to pick up incoming calls.					
Audio/Video:							
See line status (free/busy)		The other user can see if the AV line is free or busy		X* when busy, the AV icon is grayed out	X when busy, the AV icon is grayed out	X when busy, the AV icon turns red	X when busy, the AV icon turns red
see Conversation participants		The other user can see who is being talked to about AV.				X	X

 (*) These authorizations only apply within the estos UCServer service responsible for the user. Federation contacts or contacts from other estos UCServer services will not see this data!

5.2.4.6 Administratively pre-set authorizations and authorization levels

The administrator is able to allocate authorization levels or single authorizations. In this case, the administratively pre-set authorization levels cannot be minimized anymore. This means that the lowest authorization level "Blocked" cannot be selected anymore for the contacts concerned. This is because the lowest authorization level allocated by the administrator always applies.

-  If single authorizations are administratively given instead of authorization levels, the authorization level can only be changed by the administrator.
-  For contacts already authorized by administration settings there will be no authorization inquiry dialog.

5.2.5 Favorites


In the estos ProCall Attendant Console frequently used contacts can be stored at the tab *Favorites*. They can be sorted in freely defined groups. For more information please refer to *ActiveContacts*.

Special Favorites tab functions

The tab *Favorites* provides a specific function in contacts in the search results list, the context menu function **Add to Favorites** include in this tab.

Line group

A special group can be displayed in the *Favorites* tab which contains all phone lines which your system administrator has configured for you. You can display this pre-defined line group if you activate the appropriate option in the settings dialog on the View page.


Please note that your Administrator can exclusively change the contents of the group. For you the group is read only. This is by the symbol  in the title bar. If new lines are added or old ones removed, the group is automatically updated accordingly.



If the pre-defined lines do not satisfy your needs you can copy the elements into a new group which you create and then deactivate the pre-defined group in the settings dialog. Please note, however, that this is then no longer automatically updated in case of changes.

5.2.6 ActiveContacts

Contacts are displayed as *ActiveContacts* in the **Favorites** tab.



In addition to *ActiveContacts* these entries can also be telephone lines and quick dial targets.



5.2.6.1 ActiveContacts





ActiveContacts are showing the presence of a contact. Additionally they offer buttons for call establishment, chat capabilities and they grant access to the context menu offering further functions.

The tooltip help of an *ActiveContact* contains all available information in text format.

A double click on an *ActiveContact* opens a window showing the related contact details. A right click on an *ActiveContact* opens the related context menu offering further functions.






Moving the mouse over the *ActiveContact* buttons displays a tooltip help. A left click on an *ActiveContact* displays the function buttons listed below:

Icon	Description
	Call a contact by phone, plan a phone call or prepare a phone call.
	Start a VideoChat with the contact. The icon is inactive or grey if the related contact doesn't offer the

	feature, if no Video and Audio devices are available or if the feature is deactivated.
	Start a Chat with the contact.
	Schedule an appointment with the contact.
	Write a new email to the contact.
	The menu item Authorisation level enables users to change the user rights for the specific contact.

The actual presence of a contact and its services changes dynamically the availability and status of the related indicators or buttons.

Depending on the existing authorizations for this contact the following icons are displayed:

Icon	Description
Presence	The presence icon displays the contact status.
	The small phone icon displays a user's line and its status. A phone is displayed for each of the user's visible lines (maximum two). If the line is diverted the phone is complemented with a small arrow.
	The small calendar icon displays the status of the user's calendar if there is an appointment now or in the future (within 24 hours).
	The Federation icon identifies all external contacts accessible via Federation.
	If a user has not logged in using a Windows/Mac® client, or if logged in to UCServer using ProCall Mobile while in idle mode, the cell phone icon is displayed in the ActiveContact.
	The symbol indicates that the user is being informed of status changes for this contact.

5.2.6.2 Lines

If the entry represents a phone line the status of a line is displayed. Actions like e.g. setting call diversions are available at the context menu. The actions available are configured centrally by the system administrator. A double click on the entry invokes a phone call.

5.2.6.3 Quick dial numbers

The entry can be also defined as quick dial target. The use is of course not just limited to phone calls; user-defined actions on the phone system can also be triggered (e.g. door opener activated by entering the appropriate system code).

5.2.7 The Phone-Link

With the installation of estos ProCall Attendant Console on your system the additional URL Handler "phone:" is registered, which allows you to put HTML document references to phone numbers or to the contact details window. A visitor of an Internet site can be given the possibility to initiate a telephone call to a certain participant by clicking on a link, to open the contact detail window or to establish certain contacts in the Favorites.

The use of the URL handler "phone:" for dialing is analogous to "mailto:" within the anchor tag in the HTML code. The number to be dialled or the EntryIDs of the contact to be opened follows as a parameter immediately behind.

5.2.7.1 Dial with URL Handler

The phone Handler can easily select a phone number by clicking on a link. For this the phone number to be selected is given to the phone Handler as the only parameter.

Example:

You wish to create a dialing link for subscriber "John Smith" with phone number "+498912345678". Insert the following lines into your HTML code:

```
<a href="phone:+498912345678">call Jon Doe</a>
```

The example looks like this:

Call John Smith

5.2.7.2 Open contact detail window with the URL Handler

The phone Handler can also be used for opening contacts. The Entry-IDs of the contact (separated by ":") must be given to the Phone Handler.

Example:

You would like to create a link displaying the contact details of the party "John Smith".

For example, the subscriber "John Smith" has the following entry IDs:

Data base ID: DB06 (ODBC data source)

Data memory ID: ODBC (in case of ODBC: name of ODBC data source)

ContactID: 1 (ID of contact in the ODBC data source)

Add the following lines in your HTML code:

```
<a href="phone:ID:DB06:ODBC:1">open John Smith</a>
```

The example looks like this:

Open John Smith



If estos ProCall Attendant Console contains the setting that contacts are opened by default for editing, the contact in the editor of the data source (if possible) is opened instead of the contact detail window.

5.2.7.3 Add contact in the URL Handler Favorites

The phone handler can also be used to make contact in the favorites. This can optionally be contacts from the connected data sources or contact Federation contacts.

To add a contact from a data source, the keyword "addcontact:" must be given after the keyword "phone:". Afterwards, the Entry-IDs of the contact are displayed in the same way as in the contact detail window, each separated with ":". Optionally, the tab and the group name where the contact should be filed, can be given.

➔	Without specifying a tab and group name the contact is stored at the tab "Favorites".
➔	If only the tab name is given, the contact is put in the first group in the card index tab.
➔	If only the group name is given, all tabs are searched and the first group of the same name is used.
➔	If no tab or group with the given name exists, these are automatically applied.

Example:

You want to include "John Smith" in Favorites. The participant "John Smith" has the same EntryIDs like in the example "open contact detail window".

Add the following lines in your HTML code:

```
<a href="phone:addcontact:DB06:ODBC:1" > include John Smith in Favorites</a>
```

The example looks like this:

Include John Smith in Favorites

To include a Federation contact, specify the presence identity (e.g., SIP Uri) instead of the Kontakt-EntryIDs.

Add the following lines in your HTML code:

```
<a href="phone:addcontact:John.Smith@domain.com">Add John Smith to your favorites</a>
```

The example looks like this:

Include John Smith in Favorites

5.3 Use presence information


Here you find out how to control and use the presence information. Please, choose a subject:

- Own presence
- The presence of the contacts
- Presence icons

5.3.1 Own presence

The **My presence** display in the Main window shows the user's currently set presence information (or the information determined by estos UCServer) . Therefore the user can see at any time how they are visible in the system for other users. The user interface visualizes upcoming appointments, status of phones, including set call forwardings and allows access to the settings of estos ProCall Attendant Console.

5.3.1.1 My presence



- [1] My own presence
- [2] Availability/Status/Notice
- [3] Current logged in user
- [4] My lines
- [5] My audio/video devices
- [6] My chats
- [7] My calendar
- [8] My inbox
- [9] Main menu

This range consists of several parts (in the sequence of the numbering):

- **My presence**
The large presence symbol shows you your current presence state (manually set or determined from the estos UCServer). For more information about the symbols and colours used by estos ProCall Attendant Console see Presence symbols. If you click on the presence symbol the menu for presence settings and presence profiles opens.
- **Currently logged-in users with status, memo and availability**
The two lines of text contain, in the first line, the name of the user who is logged in, then below that the presence status in text form with the memo just set, if any. In addition, provided this was set, the availability stored in your presence profile is displayed as a symbol to the left of the presence status. Clicking on the name opens the "Presence settings and presence profiles" menu. By clicking on the presence status or memo text, you can immediately change the memo text. The selection list which then appears displays items of memo text which have already been used and which can be set again.
- **My line(s)**
All phone lines of the user will be shown as symbols. You can find more information about phone lines in Lines options.
- **My audio/video devices**
The item stands for the Audio-/Video devices available for Audio-/VideoChat. The item can be clicked or it can be opened per ALT+V keys to configure the usage of the Audio-/Video devices. Once the item is clicked a menu allows configuring if Audio- and Video devices are to be used (for VideoChat), if Audio devices only are to be used (for AudioChat) or if no devices are to be used (Audio/VideoChat off). The selected configuration can be changed later any time by pressing the AV device item at the My Presence area. Further an Audio-/Video Wizard can be started to store the devices to be used with Audio-/VideoChat. The tooltip on the item gives you a description of the devices you are using. Additionally the color of the item describes the actual status of the devices. If it is "green" all devices are ready to use, "red" for devices are in use and "gray" means that no devices are available. A triangle symbol is used for VideoChat, a headset symbol is used for AudioChat. For more information about Audio/Video communication see Audio-/VideoChat.
- **My chats**
Signals new text chats in Tooltip that you have received, but still haven't read. Click on the button to open a dialog box for contact selection, to be able to start a chat with a participant. Selecting several contacts starts a chat with several participants (chat room).
- **My calendar**
Shows the current diary status and permits opening the diary if available. A tool tip will show the next scheduled appointment. Moreover, you can look into the context menu (right click) and read the diary so as to selectively reconcile your appointments with estos UCServer.

- **My inbox**
Signals new emails in Tooltip that you have received, but still haven't read. Click on the button to display the email inbox.
- **Main menu**
Opens the estos ProCall Attendant Console main menu.

5.3.1.2 *Presence settings and presence profiles*

This menu can be opened with clicking on the presence symbol and is used to change the own presence state and for configuring of presence profiles.

A presence profile is formed from the presence status, a memo and a call forwarding profile. Optionally, an availability can be entered in the presence profile which is signaled and displayed to other users. Creating a separate presence profile is described later on in this section.

Presence entries

The first part of the menu displays the currently available presence profiles. There are four pre-defined profiles, one for each presence status. The menu entry describes precisely what is set on selection.

Reset status

With this, the user can reset a manually set presence state. This does not change the memo or set call redirections.

Set presence...

Opens a dialog with which all presence aspects can be set simultaneously. The user can select their status, the memo and a diversion profile here and set them by confirming with **OK**. **Cancel** closes the dialog without making changes to the presence.

Edit presence profiles...

Opens a dialog which can be used to configure presence profiles.

There are four default profiles, which can't be deleted but adopted to your needs.

The user can also create own additional profiles with the **New** button.

As well **Edit** as **New** open a further dialog which permits all aspects of a profile to be set.

5.3.1.3 *Grouping attributes*

Change grouping attribute

In the "Set grouping attribute" sub-menu, under Presence settings, you can set or again remove the grouping attribute assigned to you, provided an administrator configured this in estos UCServer. A grouping attribute is another item of information which any user can set for himself/herself and which is displayed to other users in Favorites or in other contact groups and also in the contact tooltip. The grouping attribute makes it possible for users to specify flexible properties such as team affiliation, area of responsibility and work focus and to make these visible to other users. Grouping attributes can be used to display contact groups for all grouping attributes in use and to automatically sort contacts according to the grouping attributes they set for themselves.

Extra info

In the "Set grouping attribute" sub-menu, you can enter an item of free text as additional information for a grouping attribute, provided you previously set a grouping attribute for yourself. This free text is then displayed with the grouping attribute to other users in the presence tooltip of your contact.

5.3.2 **The presence of the contacts**

Every user connected to the system has his own status, his *Presence*. This information is established according to defined rules from the status of several services: Telephone status (telephone service), calendar status (calendar service), logged on/ logged off (system service) and manually entered user status.







The presence gives information about the current availability of a call partner at any time.

An overview of the displayed presence symbols and their meaning can be found under presence symbols.



5.3.3 Presence icons

Every user connected to the system has his own status, his *Presence*. This information is established according to defined rules from the status of several services: Telephone status (telephone service), calendar status (calendar service), logged on/ logged off (system service) and manually entered user status. The presence therefore dynamically informs of the availability of a communication partner depending on the current status of the various services.



Possible presence states



Status color	Meaning
	Available
	Busy
	Out of office
	Inactive
	Do not disturb
	Presence information unavailable

In addition to this presence information the following additional icons are used in estos ProCall Attendant Console:







Icon	Meaning
	If a contact is not logged on to a server their status is displayed with a gray symbol.
	If a contact receives a call on one of their lines their status flashes red/orange

Optionally, a user can set, in his or her presence profile, an availability which is signaled to other users. This availability can describe the following statuses:

Icon	Meaning
	Break: The user is currently on a break and probably cannot be reached.
	Business trip: The user is currently on the road and may not be available.

	Home office: The user is working from home and can be reached there.
	Vacation: The user is currently on vacation and is therefore unavailable.

Besides to the contact-based presence information the telephone lines shows a different status:

Icon	Meaning
	Phone line ready, no active conversation
	Active conversation (external or internal)
	Changing between red and orange - incoming ringing
	Line faulty
	Active call redirection
	Active call protection (the icon for the redirection is not displayed with active call protection).

5.4 Plan communication










Here you can find out how to plan and track your communication with estos ProCall Attendant Console. Please choose a subject:





- Journal
- Journal browser
- Journal editor
- Call planning
- Reminder window

5.4.1 Journal




The **Journal** tab in the main window shows the last calls and chats. It contains the most important information in a view. The entries are always grouped by days.

The calls displayed use the same icons on the **Journal** tab as in the journal browser.

-  Incoming calls (connected)
-  Incoming missed (not connected) calls
-  Outgoing calls (connected) and calls (not connected)
-  TextChat
-  Incoming audio chats (connected)
-  Incoming missed audio chats (not connected)
-  Outgoing Audio Chats
-  Incoming video chats (connected)
-  Incoming missed video chats (not connected)






-  → Outgoing video chats
-  ← Incoming screen sharing (connected)
-  ! Incoming missed screen sharing (not connected)
-  → Outgoing screen sharing

The **Journal** tab can filter the shown entries with various options:

-  **Today**
Click here to display just the calls which were made or taken today.
-  **Last week**
Click here to display just the calls which were made or taken in the last seven days.
-  **Last month**
Click here to display just the calls which were made or taken in the last 31 days.

With estos ProCall Attendant Console it is possible to filter journal entries with a freely defined text. For example type '123' into the input field of the filter options to reduce the contents of the view to entries which are containing the text '123'. Please note that using the free text filter in this view only affects the currently loaded data and hides unwanted rows for a quick access. For a complete full text search in the complete database please use the journal browser instead.



In the **Journal** tab you can configure the shown columns. You can reposition a column by left click and hold the left mouse button on the column header. Now move the mouse to the desired position. To remove a column, just move it outside the table. Right click on a column header opens a context menu. There you can change the visibility of columns and you can set the columns and their grouping options back to default. With this context menu you can open the field selection dialog. Here you can drag and drop column headers in to the table to add these columns to the view.












	Unlike the journal browser, the Journal tab does not have to be updated manually. New journal entries are entered automatically.
	Unedited calls and chats will be shown in bold.
	Calls which are answered by other users are shown in blue.
	Journal entries can be sorted by clicking on their column headers (reverse order it by click again). Please note, that journal entries are sorted within their grouping setting (per day).
	Please note that the journal in the main window is only a brief view of the journal entries. You will find a detailed journal with all columns and journal entries in the Journal browser.

5.4.2 Journal browser












The journal browser of estos ProCall Attendant Console offers a more detailed view on your calls and chats than the journal tab in the main window. Here you can get all calls of arbitrary time frames and you can group them with differently, not only by days.







The calls displayed use the same symbols in the Journal browser as in the main window:

-  ← Incoming calls (connected)
-  ! Incoming missed calls (not connected)

-  → Outgoing calls (connected) and calls (not connected)
-  TextChat
-  ← Incoming audio chats (connected)
-  ! Incoming missed audio chats (not connected)
-  → Outgoing Audio Chats
-  ← Incoming video chats (connected)
-  ! Incoming missed video chats (not connected)
-  → Outgoing video chats
-  ← Incoming screen sharing (connected)
-  ! Incoming missed screen sharing (not connected)
-  → Outgoing screen sharing

The journal browser has a series of filters with whose help certain calls can be displayed or hidden depending on their type.





-  **Default**
Clicking on this button will reset all type-based filter settings to their default values. All calls that you have made will also be displayed again.
-  **Incoming calls**
Activate this option to display just incoming calls. Deactivate this option to display both incoming and outgoing calls.
-  **Outgoing calls**
Activate this option to display just outgoing calls. Deactivate this option to display both incoming and outgoing calls.
-  **Internal calls**
Activate this option to display just incoming calls. Deactivate this option to display both incoming and outgoing calls.
-  **External calls**
Activate this option to display just external calls. Deactivate this option to display both external and internal calls.
-  **Calls (not connected)**
Activate this option to display just calls which were not connected. This also contains all missed calls. Deactivate this option to display both calls which were connected and calls which were not connected.
-  **Calls (connected)**
Activate this option to display just connected calls. Deactivate this option to display both calls which were connected and calls which were not connected.
-  **With note**
Activate this option to display just calls for which call memos were saved. Deactivate this option to display both calls with and calls without call memos.
-  **Without note**
Activate this option to display just calls without call memos. Deactivate this option to display both calls with and calls without call memos.
-  **Phone number hidden**
Activate this option to also display phone conversations that block the partner's phone number. Deactivate this option to only display those conversations that provided the partner's phone number.
-  **Public entries**
Activate this option to also display calls by other estos ProCall Attendant Console users. Please note that private calls by other estos ProCall Attendant Console users are not displayed. Equally, the journal entries of other estos ProCall Attendant Console users cannot be changed as a rule. Deactivate this option to only display your own phone calls.

-  **Filter journal type**
Use this feature to filter journal types. By default, all journal types will be  displayed. Journal type options include:  TextChats only,  AudioChats only,  VideoChats only or  phone calls only.

In addition, estos ProCall Attendant Console supports further functions for finding journal entries:

- **Date filter:** Select the desired start and end date in the date fields in order to display just journal entries from within a certain period. Alternatively you can also use the pre-defined keys **Today**, **Last week** or **Last month** to set the time period.
- **Text filter:** You can filter journal entries by a freely defined text. For example, type in the name of a sought after contact into the text field and press Enter. Alternatively you can start the search by pressing the **Start search** button.

The journal browser has the ability to group journal entries by certain criterias. You can change the grouping option in a drop down box in the area **View**.





-  **Group by days**
All journal entries from the same day are grouped together.
-  **Group by contacts**
All the same conversation partner's journal entries are grouped together.
-  **Group by project**
All journal entries assigned to the same project are bundled.
-  **List view**
The journal entries are displayed without grouping.

More journal entries

By default, a maximum of 100 hits will be returned from searches by estos ProCall Attendant Console. All additional journal entries corresponding to the search criteria can be requested by clicking the **Additional Journal Entries** button. That button is on the status bar. The button will be hidden when all log entries have been displayed.

The print function in the journal browser enables you to print either everything or only the selected journal entries as a list. It is printed the same as it is displayed on screen, i.e. with the current groupings and all visible columns.

You can freely change the columns to view in the journal browser. You can reposition a column by left click and hold the left mouse button on the column header. Now move the mouse to the desired position. To remove a column, just move it outside the table. Right click on a column header opens a context menü. There you can change the visibility of columns and you can set the columns and their grouping options back to default. With this context menu you can open the field selection dialog. Here you can drag and drop column headers in to the table to add these columns to the view.

	Unlike the Journal tab in the main window the journal browser must be updated manually, especially if new journal entries are added.
	Calls and chats marked as Unprocessed are highlighted in bold type.
	Calls which are answered by other users are shown in blue.
	The journal entries can also be sorted if you click the column headers (reverse sorting on second click). If a grouping has been set, the journal entries within each group are sorted according to the sort criterion.










The grouping after projects is only available when the settings to Projects were configured that should use estos ProCall Attendant Console projects.

5.4.3 Journal editor


The journal editor in estos ProCall Attendant Console permits you to look up and subsequently edit information on a call made or received. It can be opened by double click on the journal entry of a journal list for example.

If a contact was linked to the opened journal entry, all functions for the contact can be run via the tool bar. For detailed descriptions of these functions, please refer to Contact details.




In addition, you will find special functions in the icon bar which you can execute for a journal entry:

-  **Save**
Click here to save all changes to the journal entry.
-  **Save and close**
The journal entry is saved and the editor window is subsequently closed with this function.
-  **Print**
Click here to print out the journal entry.
-  **Print preview**
Click here to show a print preview of the journal entry. You can also print the journal entry from the preview.
-  **Printer settings**
Click here if you wish to change the printer settings for printing the journal entry.
-  **Edited**
If this button is activated the journal entry is marked as processed. Activate this button if you wish to mark the journal entry as processed.
-  **Unprocessed**
If this button is activated the journal entry is marked as unprocessed. Activate this button if you wish to mark the journal entry as unedited. Unprocessed journal entries are displayed in bold type in the journal view.

The following data in the journal entry can be changed or added to with the journal editor:

-  **Link contact**
When the contact selection button is clicked the contact selection dialog opens where you can link the selected contact to the journal entry by clicking **Ok**. Please note that this process transfers both the contact name and also the company name from the selected contact in the journal editor. If a contact is linked to a journal entry, all contact related functions can be executed from within the journal entry. So you can call the contact with a different phone number again or send him an email.
- **Change contact name**
You can enter any name in the contact name field which also appears in the journal views. Please note that the contact name can thus deviate from the name of the linked contact.
- **Change company name**
You can enter any name to be stored in the journal entry in the company name field. Please note that the company name entered may thus be different from the company name of the linked contact.
- **Change project PIN**
You can assign the call to a particular project here. You must first define the projects for this. You can create new projects in the settings under Projects.
- **Mark private call**
If this option is activated the call can be marked as a private call. This means that other estos ProCall Attendant Console users can no longer see this entry. Please note that depending on the server settings, all contact data including phone numbers can be shortened or deleted by this.






- **Edit call memo:**
Enter your call memo in the journal editor's memo field.

	Please note that you cannot change the journal entries of other estos ProCall Attendant Console users.
	Please note that the project PIN can only be changed if this feature has been activated in the settings on the Projects page.
	It is only possible to mark private calls if this feature has been activated in the settings on the Projects page.

5.4.4 Unprocessed calls and chat



You will find phone calls and chats which require your particular attention on the **Unprocessed** tab. Depending on your settings, you will see all journal entries here that are marked as not dealt with or all "Call in absence" e-mail marked "not read". Further information can be found under Settings in the Incoming calls.

You will find the following functions on the **Unprocessed** tab's icon bar:

-  **Mark as edited**
The selected entry or entries are marked as processed or read. The entries thus disappear from the view.
-  **Mark all as edited**
Marks all entries in the view as processed or read. The view is then empty.
-  **Internal calls**
Activate this option to additionally display internal calls. Deactivate this option to display just external calls.
-  **Grouped by days**
Click here if the entries in the list are to be grouped by day.
-  **Grouped by contacts**
Click here if the same subscriber's entries in the list are to be grouped.

In this view of estos ProCall Attendant Console it is possible to filter the entries with a freely defined text. For example, if you type in '123' into the input field of the filter options, you will only see entries which contain '123' in one of their fields.

In the tab **Unprocessed** you can freely configure the displayed columns. You can reposition a column by left click and hold the left mouse button on the column header. Now move the mouse to the desired position. To remove a column, just move it outside the table. Right click on a column header opens a context menu. There you can change the visibility of columns and you can set the columns and their grouping options back to default. With this context menu you can open the field selection dialog. Here you can drag and drop column headers in to the table to add these columns to the view.








	An overview of the entry icons can be found on the Journal.
	The phone calls can also be sorted if you click on the column headings (reverse sorting on second click). If a grouping is defined the phone calls within each group are sorted by the search criterion.

5.4.5 Call planning

5.4.5.1 Plan call






With the help of the *call planning* window you are able to mark calls which you wish to make in the future. Already planned calls can be viewed in the tab **Planned** in the main window.

You will find all the functions which you can use for a planned call in the editor's icon bar


-  **Make call**
Click the upper half of the button to call the subscriber. The phone number which was specified in the phone number field in the editor dialog is always used.
In the lower half of the push button, you are able to view the contact context menu with the arrow. Here, you will find every activity available for the linked contact. For a detailed description of these functions, please refer to contact details.
-  **Save**
Click here to save the planned call and all changes. The saved call appears on the tab **planned** in the main window.
-  **Save and close**
The planned call is saved with this function and the editor window is then closed.
-  **Print**
Click here to print out the planned call.
-  **Print preview**
Click here to display a print preview of the planned call. You can also print out the planned call from the preview.
-  **Printer settings**
Click here if you wish to change the printer settings for printing the planned call.
-  **Delete planned call**
Click here to delete the planned call. The editor window is then closed. Please note that this action cannot be undone.

Change the status of the planned call

In the section **Status** on the tool bar, the status of the planned call can be define with the aid of the drop-down box:

-  **Set to in process.**
Select this entry if you wish to show that you are currently processing the planned call.
-  **Mark as completed**
Select this entry if you wish to show that you have successfully processed the planned call.
-  **Mark as not started**
Select this entry to indicate that the planned call is pending.
-  **Mark as waiting for someone else**
Select this entry if you have to wait for someone before you can make this call.
-  **Mark as deferred**
Select this entry to mark the planned call as postponed.

The following data for the planned call can be defined or changed with the editor:

- **Change subject:**
The topic field is generated automatically when creating a new planned call. You can customise this according to your requirements here.
-  **Link contact**
Clicking the contact selection button opens the contact selection dialog with which you can link the selected contact to the planned call by confirming with "OK". Please note that both the contact name and also the company name are transferred from the selected contact to the editor by this process.






- **Change contact name**
You can enter any name in the contact name field which also appears in the journal views. Please note that the contact name can thus deviate from the name of the linked contact.
- **Change company name**
You can enter any name which is to be saved in the journal entry in the company name field. Please note that the company name entered can thus deviate from the name of the linked contact.
- **Change phone number**
The phone number which is dialed when the upper half of the Call button is clicked is shown here. If you have linked a contact to this planned call you can dial one of the contact's phone numbers in the dropdown list. You can nevertheless also enter any phone number in the field.
- **Define start date**
Enter the start date in the relevant field. This defines when the planned call is to be made. Alternatively you can open a calendar via the dropdown arrow and simply select a day.
Note: If neither a due date nor a reminder date have been activated, these will also be entered automatically when selecting the starting date.
- **Enter date due**
Define here by when the planned call should have been made. You can either enter the date directly or use the calendar which you can open via the dropdown arrow.
Note: if you have not yet defined a reminder date this is automatically set when the due date is selected.
- **Set reminder**
Activate this option and enter the reminder date with a time to be reminded of the call. The Reminder window opens at the given time. Please note that the reminder function is only performed for planned calls which are marked as not processed.
- **Change project PIN**
Here you can assign the planned call to a particular project. You must first define the projects for this. You can create new projects in the settings under Projects.
Please note that the project PIN can only be changed if this feature has been activated in the settings on the Projects page.
- **Change memo**
Here you can enter a memo text for the planned call which you wish to save.

5.4.5.2 Planned calls

The tab **Planned** gives an overview of all phone calls which are planned with estos ProCall Attendant Console.

Display of planned calls



The planned calls have different icons depending on the processing status:

-  **In progress**
The planned call is presently being processed.
-  **Completed**
The planned call has been successfully processed.
-  **Not started**
Processing of the planned call has not yet begun.
-  **Waiting**
Waiting for someone else to process the planned call.
-  **Deferred**
Processing of the planned call has been postponed.






In addition, the planned call is highlighted differently depending on its status:

- Planned calls which have not yet been processed are shown in bold text
- All planned calls due in the past which have not been completed are highlighted in red.
- Completed planned calls are crossed through and appear light grey.



The view on the "Planned" tab can be customised. Entries which fulfil certain criteria can be shown or blanked out.

-  **Without date or reminder**
Activate this option to also display all planned calls which have neither a date nor a reminder set.
-  **Completed calls**
Activate this option to additionally display all calls which have already been marked as completed.

The status of the planned calls can be changed via the icon bar or the context menu. Mark the relevant entries in the list and click the appropriate button.

-  **Set to in process.**
Select this entry if you wish to show that you are currently processing the planned call.
-  **Mark as completed**
Select this entry if you wish to show that you have successfully processed the planned call.
-  **Mark as not started**
Select this entry to indicate that the planned call is pending.
-  **Mark as waiting for someone else**
Select this entry if you have to wait for someone before you can make this call.
-  **Mark as deferred**
Select this entry to mark the planned call as postponed.

Further functions for processing planned calls are available in the icon bar:

-  **Delete**
Select this function to delete the selected entries. Please note that the deleted entries cannot be restored.
-  **Update**
Click this button to update the view.

In this view of estos ProCall Attendant Console it is possible to filter the entries with a freely defined text. For example, if you type in '123' into the input field of the filter options, you will only see entries which contain '123' in one of their fields.

In the **planned** tab columns can be freely configured. You can reposition a column by left click and hold the left mouse button on the column header. Now move the mouse to the desired position. To remove a column, just move it outside the table. Right click on a column header opens a context menu. There you can change the visibility of columns and you can set the columns and their grouping options back to default. With this context menu you can open the field selection dialog. Here you can drag and drop column headers in to the table to add these columns to the view.


- ➔ Either the estos ProCall Attendant Console editor or the Outlook® editor opens to edit the planned calls depending on your settings in the Planned section.
- ➔ The planned calls can also be sorted if you click on the column headers (reverse sorting on second click). Please note that the planned calls are sorted within their group, in other words per day.



5.4.6 Reminder window


The reminder window reminds you of calls which you have planned. It is always displayed when a reminder for a planned call is shown. The calls are displayed in a list.




Planned calls are highlighted differently in the overview. Details about this can be found in the help file for the call schedule.

You will find the following functions in the icon bar:

-  **Make call**
Click the upper half of the button to call the subscriber. The phone number which was specified in the phone number field of the planned call is always used.

In the lower half of the push button, you can call up the contact context menu with the arrow. Here, you will find any operations available for the contact. For a detailed description of these functions, please refer to Contact detail window
-  **Open planned call**
Click this button to open the call schedule in the list. Alternatively you can also open a call with a double-click on the list entry.
-  **Remind later**
Use this function to be reminded of the planned call again later. Mark the relevant entries in the list and select the appropriate time period for this.

You can also switch off the reminder for the planned calls. Select **Do not remind again** from the menu for this.
-  **Delete planned call**
Use this button to delete the selected planned calls from the list. Please note that this function cannot be undone.

	When you close the reminder window it is first displayed again when a reminder for the next call is due.
	A complete overview of all planned calls can be found in the main window in the "Planned" tab.
	The reminding time can be changed if you open the planned call in the editor. Further information under Planning calls.

5.5 Communicate

Here you can find out how estos ProCall Attendant Console can support you in your daily work. Please, choose a subject:


- Call window
- Line settings
- Call forwardings
- Remote Office
- Chat, SMS, E-Mail
- Audio-/Video conversation window
- Screen Sharing

5.5.1 Call window

The call window is the information and control centre for your phone calls. In addition to the visualisation of the call state, dialog partner and other relevant informations about the call, it is also possible to control the call. The window combines logically related telephone conversations in one interface and in this way allows

the convenient control of one or more conversations on a telephone. With the option of making project assignments, selecting private conversations and writing memes, this window is a central element of estos ProCall Attendant Console.

5.5.1.1 Call window overview:




- [1] Call state
- [2] Active line
- [3] List of calls
- [4] Control
- [5] Call Memo / Project settings

The call window, as shown above, is divided vertically into three areas.


- A list of calls
The call window can manage and control one or more calls or even a conference call. All calls which belong together are displayed in a call window.
- Phone control The call control area enables you to control the active call.
- Memo area with project, private labelling, phone number display suppression
The memo area extends the phone information and control with a collection of information about the call. The memo entered is written into the journal of all call participants when the window is closed. If finished calls are removed from the call window, the given note is stored at that time. To be able to set projects and mark private calls adds to the information pool. For more information about the project settings and private settings see Projects.

In this area you still have the option of suppressing the display of your phone number by switching on the phone number display suppression. The remote station called then does not see who is calling. (Does not work with every phone system and not with internal calls).

Icon	Meaning
------	---------

123 	Phone number suppression deactivated
123 	Phone number suppression activated

5.5.1.2 **Overview of the individual call in the call window:**



- [1] Call partner
- [2] Contact chooser
- [3] Phone number
- [4] Call duration
- [5] Hide contact details

- **Status icon**
The status icon shows the current state of the call. A list of status icons used can be found here. Apart from the visualisation, you can open the journal created for the current call participant via the icon. If the window contains several calls you can select a call by means of the icon and call this contact again. A tooltip on the icon displays a brief summary of the most important call information.
- **Call partner**
estos UCServer and estos ProCall Attendant Console search automatically for a contact for the phone number during a call. The contact found is displayed here if available. If no contact could be found you can create a new contact here.
You can read about which data sources can be searched in which order during a contact search in Contact search. If several contacts are found a button appears next to the contact to enable selection of a contact.
- **Contact selection** If several contacts are found for the current phone number, you can select a particular dialog partner by means of the contact selection. estos ProCall Attendant Console stores this selection and will show you this contact as your dialog partner the next time he calls again. Further information about searching for contacts in estos UCServer and ProCall Attendant Console can be found under contact search.
- **Number** The number is displayed next to the status icon. The tooltip always contains the call status and number.
You can change the dialog partner's number for a prepared or ended call here. A new contact search is automatically triggered if you change the number.
- **Call duration** Displays how long you have been connected with the dialog partner.
- **Show contact details** One of the strengths of estos ProCall Attendant Console is the option of extending the call window with dynamic HTML content. You can show and hide the display of additional information with this button. A series of templates are available for displaying further information which you can adapt to your needs.

The template defines which contact details are to be shown. You will find the templates in the installation directory in *Templates/default/*:

- *RemoteContact.xslt*
Is used in the call window for preprocess details for the current dialog partner. The template defines which contact details are displayed.
- *HoldContact.xslt*
Is used in the call window to preprocess the details for a dialog partner on hold. The partner on hold is displayed if a further estos ProCall Attendant Console user holds a subscriber while calling you. The template defines which contact details are displayed.
- *LocalContact.xslt* Is used in the call window to preprocess details for the contact called. In case of an incoming call the contact called is displayed if a contact's number is found. For this you must activate the hotline services in the settings for incoming calls. The template defines which contact details are displayed.
- *RedirectedContact.xslt* Is used in the call window to preprocess the contact details for a forwarded call. The contact for whom the call was last signalled is displayed. The template defines which contact details are displayed.


The contact data and call data provided in XML are implemented by the software in the template. If the template data contains data to be displayed, it is shown in the call window (if applicable).

In order to make customisation of the call window templates as simple as possible, you can display the XML contact and call data provided and also the result of the XSLT parser. Copy the appropriate template out of the default directory into the template folder, open it and change the value of variable *debug* in the body tag to 1:

```
<body minwidth="0" minheight="0" maxwidth="0" maxheight="0" debug="1">
```

After you have reloaded the contents of the call window by pressing F5, the displayed templates appear with a colored background. A context menu permits you to view the source code. The upper part of the text file contains the parsed template; the lower part contains the raw XML data which was handed to the parser. Further information on developing your own XSLT templates can be found [here](#).

5.5.1.3 Conference
















- [1] Conference controller
- [2] Conference participant
- [3] Controls for the conference



The call window is displayed in the format shown above as soon as you initiate a conference. You can no longer directly control the individual calls but only the conference which is displayed as the uppermost entry in the call list. How long the conference has been running is shown next to the number of conference participants. The further elements of the call window are similar to those described above.

5.5.1.4 The various control options:

Depending on the telephony status you can perform various control actions on the current call. The visibility of the individual buttons is significantly influenced by the function range of the phone system.

Icon	Meaning
	Set up dialing for the phone number currently stored in the call window:
	The currently selected contact in the call window offers several numbers. Via the icon select you can choose another of the contact's phone numbers. The call is not yet initiated. The icon call starts the call.
	Accept an incoming call. The phone switches to hands-free mode. Analogue phones do not support this feature.
	End current call. Reject incoming ringing call. End consultation call End conference.

	End auto-dial.
	The current phone status either permits ending various calls or you can connect subscribers to each other by hanging up. The combo menu displays which actions are supported. The hang-up key ends the current call.
	Hold current caller. The subscriber is either put on hold or a callback is initiated depending on the phone system.
	Retrieve subscriber on hold
	Begin callback. A window opens for searching for contacts or entering numbers. The window contains the last targets for callbacks and forwardings.
	Call on hold. Current call participant is on hold and call participant which was on hold gets connected.
	Initiate conference. Initiate a conference with the current dialog partner and the dialog partner on hold.
	Add dialog partner to the conference being held.
	Forward call. A window opens for searching for contacts or entering numbers. The window contains the last targets for callbacks and forwardings.
	Forward call. You have access to your contact's further phone numbers via the check box. Thus, you can quickly forward a call on your cordless or mobile phone. The Forward button opens the contact dialog as described under <i>Forwarding</i> .
	If the number called is engaged you can start automatic redialing via this icon. An attempt is made to call the subscriber again after a certain period of time. At what intervals and how often this redialing should take place can be defined in the settings Outgoing calls define.
	Activates the Callback when no answer or engaged function. A callback to this subscriber is started as soon as the remote station is available again.
	Planning a new call to the current contact's last connected number. If the select button is visible, you can choose one of the contact's other phone numbers for the planned call.
	The current call will be restored to the planned status e.g. for setting other project settings. If the select button appears, you can choose other phone numbers of the contact for planing the call.
	Begin call recording. If call recording is set up on the server, you can thus start call recording which is sent to you as an e-mail after the end of the call. This is possible both with a dialog partner and a conference.
	End current call recording.

	<p>Opens a dialog for subsequent selection of DTMF tones. Input can be made with both the keyboard and the mouse.</p>
	<p>If various buttons are not visible either the current phone status or the phone system driver do not permit this action.</p>

5.5.2 Line settings

All lines assigned to the user or computer are indicated as icons in My Presence. These change color in accordance with the telephone status of the line. Many different operations can be carried out on this line via the menus opened with a click.

5.5.2.1 Entries in the line menu:

- **Set as default line**
If a user has more than one line, he can define via the menu which one is to be the standard line. All telephone operations not requiring specification of the user's own line relate to this line. The line is shown in bold type.
- **Telephony control**
If a line is busy with a call, you can only have a controlling influence on the call on this line. No other operations are offered.
- **Set call diversion...**
Permits direct set-up of call diversion without having to configure a Call diversion profile. The last call diversion is saved and automatically recorded in the last dialog.
- **Cancel call diversion**
Shows all items of call diversion set up on this line. If the call diversion set up can be attributed to a Call diversion profile, the name of the profile is displayed.
- **Set call forwarding**
Shows all configured Call diversion profiles currently set up on the line.
- **Switch protection against incoming calls on/off**
Permits activating or deactivating protection against incoming calls on the line.
- **Remote Office**
Redirects the extension to a phone outside of the company. Outgoing calls will display the company's number. Further details can be found under Remote Office.
- **Configured feature codes**
If feature codes for your telephone system were configured on the estos UCServer these will be displayed here.
- **Activate/deactivate suppression of phone numbers**
This allows you to activate or deactivate caller ID suppression for outgoing calls on the line. You will see in the menu whether caller ID is displayed or suppressed. You must activate the caller ID suppression feature in the Settings.
- **Extended settings**
 - **Configure call forwardings...**
Allows configuration of Call diversion profiles.
 - **Rename line...**
Here, you can change the name for the line. That way, it is easier to distinguish between different terminals using the same phone number.

5.5.3 Call forwardings

Call diversions can be set in several contexts in estos ProCall Attendant Console.

Call diversion profiles have been integrated to support the User in being able to reuse several different often-used call diversions and at the same time to be able to divert several lines.

If a call diversion is to be set on one of your own lines this can be done via the lines button in the "My presence" area.

This opens a dialog which lists the currently available call diversions and allows them to be reset or edited.

A call diversion profile consists of a name, the line which is to be diverted (or the lines which are to be diverted), the type of diversion and the target phone number.

New

With **New** a new call diversion profile can be established. This opens a dialog. In this dialog, the user defines the name of the profile and selects the line to be forwarded. He can also select **All** if he has several lines and wishes to forward calls from all of them.

Edit

The currently selected diversion profile can be edited with this icon.

Delete

Deletes the selected profile.

5.5.4 Remote Office

The Remote Office makes it possible to work on the road or at the home office. With this function it is possible to use any other telephone (remote office telephone) instead of your own phone.

This feature can be turned on and off from Line Settings. If the feature is not visible there, the telephone system does not support it.

If the feature 'Remote Office' is turned on, the behavior will change as follows:



- Calls to your phone will be forwarded to the Remote Office phone.
- If the PC is used to select phone number, the Remote Office Phone will ring first. If the call is answered, you will be connected with the selected phone number.

5.5.5 Chat, SMS, E-Mail


The message system in estos ProCall Attendant Console allows conversations (Chat) between two and up to 30 participants. If individual users are not logged in while the conversation is ongoing, they are shown all conversations after logging in. Participants can be added to or removed from the conversation at any time.

5.5.5.1 Start chat

There are various ways of initiating a chat.

-  **Chat to a single user:**
Everywhere you see another user or contact in estos ProCall Attendant Console you can begin a chat with this user via the context menu or via the ActiveContacts icons. This is possible in any presence state of the contact. In the presence state *Do Not Disturb (DND)* the message may be delivered later. If the Chat icon is clicked the **Chat window** opens. At the text field the message can be entered. Once finished the icon *Send* can be pressed. By pressing the *Smiley* button, a smiley from the Smilies list and added to the message. The message sent and the message received by remote users will be displayed with contact name and time stamp in the upper text chat message window. If either Audio- or Video-Chat are available, a request to use those chat modes with the contact can be sent using the corresponding green button (see the corresponding information below).
-  **SMS text to a single user:**
Everywhere you see a contact in estos ProCall Attendant Console you can send him a SMS text via the

context menu or via the ActiveContacts. For this purpose the context menu offers all phone numbers which are to be found in the mobile phone number fields for the contact.

-  **Chat with a group**
At the Favorites you can start a chat with the user group via the context menu of a group. Only internal users will be added.



To be able to send a SMS message to a user your user profile at the estos UCServer need the authorisation from the system administrator.



The Audio/VideoChat feature is available only if it has been enabled, if Audio and Video devices are installed and if the system administrator granted the right to use it. How to change the Audio/Video functionality is described in chapter Presence at the bullet point *Audio/Video devices*. How to configure the Audio/Video devices for the usage with the Audio/VideoChat is described in chapter Audio/Video Wizard.

5-5-5.2 *Chat status*



Messages sent by the user always have a status that is indicated with an icon in the status bar of the message or of the message block. The meaning of the icon is given in the tool tip.



The "read" status of a message is not transmitted for participants who are reached via Federation and thus not signaled.

5-5-5.3 *Chat with a group*

Every chat participant can add or remove other users to/from the chat room or exit or rejoin the chat room later. The chat room can also be given a descriptive name, for example to be able to find it again later in the journal.

-  **Add party**
After clicking the button to add users the search dialog opens in which you can see all internal users. Select one or more users and confirm the dialog to add the participants.
Chat parties can be added per drag & drop to the Chat window (sending SMS messages for mobile contacts only, a estos UCServer Chat for internal users only).
The maximum number of participants is limited to 30.
-  **Remove participant**
To remove a subscriber from the chat open the subscriber's context menu and select the relevant entry.
- **Join chat room**
If you have exited a chat room or were removed from the chat room by another participant, you can rejoin the chat room. You will find this function in the "Further Actions" menu.
- **Leave chat room**
If the chat room was created by sending the first chat message, you can exit the chat room at any time. Then you will no longer receive any messages of other participants. You will find this function in the "Further Actions" menu.
- **Set or modify chat room names**
You can name or change the name of a chat room at any time, provided you are a participant of the chat. To make changes, click in the Name line of the chat, which you will find above the participant list.

5.5.5.4 Chat messages

- **Delete chat history**
You have the option, both in a chat with a single user and also in a group chat, to delete the entire chat history, by using the "Delete chat history" button which can be found in the "Further actions" menu. The chat history is only deleted from your view, and the action does not affect the chat history of your other chat partners.
- **Delete individual chat messages**
If you want to delete specific chat messages, move your mouse over the message you want to delete. This will cause a red X symbol to appear, which you can use to delete your message. The message will only be deleted from your view; and the action does not affect the chat record of your other chat partner.



Please note that no chat rooms can be created with Federation users and no Federation subscribers can be added to a chat room.

5.5.5.5 Links:

estos ProCall Attendant Console supports the following links in the chat window:

- **Phone numbers:**
Phone numbers are highlighted as such and can be selected by clicking them as long as they comply with the rules for the currently selected line's location. (phone:+4912345612, +49 123 456 - 12, 12 etc.)
- **E-mail links:**
E-mails are recognised and the default mail program is started by clicking it. (mailto:info@info.de, info@info.de etc.)
- **Web links:**
Recognises all Internet links such as. (http:, https:, www:, www2:, file:, ftp:, gopher:, ntp:, prospero:, telnet:, news:, wais:)
- **UNC paths:**
Recognises UNC paths. (\\server\directory\file)



If links contain whitespaces estos ProCall Attendant Console cannot find the beginning and the end of the link itself. If you place these links between < and > brackets the link is correctly recognised. <Link with space(s)>



To be able to chat with one participant, the Public authorization level must have been granted, at least. This authorization level may also be set administratively for internal users using global settings or group policies (see also Authorizations).

5.5.6 Audio-/Video conversation window

The Audio-/Video conversation window is active while an Audio-/VideoChat conversation is present. Using the AudioChat mode no Video area is displayed thus the AudioChat window size is smaller than the VideoChat window size. But the usage for establishing Audio/VideoChats and the device handling is identical between Audio and VideoChat. The Audio/Video conversation window comprises of the contact area at the upper left corner and below a coloured keypad for Audio/VideoChat call control (e.g. accept calls, hang-up calls), a Text Chat area, below an area for Screen Sharing and a status line at the bottom. If Video is present the conversation window includes a video area at the right side including control buttons (overlays) becoming visible once the mouse moves over. The Chat area (text mode) at the left lower side can be used in any call state. If multiple video streams are shown (e.g. camera views and a shared screen) the major video picture can be changed by clicking on one of the minor video pictures. If the Audio-/Video conversation window is




maximized the view changes to full screen mode. The full screen mode can be stopped by pressing the Escape key. The text based chat doesn't depend on any callstates and can be used any time.

Several Audio/VideoChats are supported simultaneously. Each Audio/VideoChat is represented by a conversation window. Only one conversation window can be active at the same time. Additional calls are in "on hold" state. If another call is accepted additionally to an existing call, the first call is automatically placed on hold. A call that is on hold can be activated by a "Retrieve" button.

In addition to the described methods how to accept and reject calls some USB devices offer the possibility to control the calls with device buttons (Human Interface Device "HID" buttons). This means that an Audio-/VideoChat can be accepted or dropped per device button. The microphone can be muted per device button. The supported devices and how to configure them can be found at the chapter Audio/Video Wizard, call control per device buttons.


5.5.6.1 Incoming Audio-/VideoChat

An incoming Audio-/VideoChat opens the AV conversation window. At the left upper corner the calling contact is displayed. A specific ringer sound plays at the speaker standard device to indicate the incoming Audio-/VideoChat to the user. While ringing an incoming VideoChat the local picture is shown at a large Video area at the right side of the window. The picture appears to be mirrored in order to allow users to check their appearance as using a real mirror:

-  **Accept an AudioChat**
If the green button with the headset and text has been pressed for accepting calls, the call will be accepted. The status bar on the bottom left indicates the quality of the media connection.
-  **Accept VideoChat**
If the green button with the triangle and text has been pressed for accepting calls, the call will be accepted. The status bar on the bottom left indicates the quality of the media connection. The local video image will be small and the remote participant's video image will appear large. The local Video area can be hidden by pressing a small triangle item at the lower right side of the large Video picture. The triangle item is a toggle button thus once pressed again the local video area appears back again.
-  **Reject an Audio/VideoChat**
If the red button with the rectangle and text has been pressed for rejecting calls, the call will be rejected and the audio- or video-chat window will be closed.








5.5.6.2 Outgoing Audio-/VideoChat

With an outgoing Audio-/VideoChat the AV conversation window opens. At the left upper corner the called contact is shown. A specific ringback sound is played at the configured Audio device (e.g. headset) as soon as the remote device could be contacted and rings. If VideoChat is used the local picture is shown at the large right Video area. While running an outgoing VideoChat the local picture is shown at a large Video area at the right side of the window. The picture appears to be mirrored in order to allow users to check their appearance as using a real mirror. During the call establishment phase several operations are possible:

-  **Hang-up the Audio/VideoChat**
If the red button with the rectangle item is pressed the outgoing Audio/VideoChat is disconnected and the Audio/Video conversation window is closed again. The called contact finds a small "bubble" message at the Windows® system tray in order to allow a comfortable call back per mouse click.


5.5.6.3 Connected Audio-/VideoChat

If the called contact accepted the Audio/VideoChat the parties can communicate with each other. Several options are possible:

- 
Hang-up the Audio/VideoChat
 If the red button with the rectangle item is pressed the Audio-/VideoChat is disconnected and the Audio/Video conversation window is closed again. A specific disconnect sound is played to the Audio standard device indicating the closed call.
- 
Quality and status line
 During an Audio-/VideoChat the quality of the data stream is indicated by a small triangle bar item. The more black bars are shown the better is the data stream quality. Moving the mouse over the item additional information is presented to the user as tooltip text: overall quality (good/bad), transmit statistics ("TX" values), receive statistics ("RX" values), Codec used(e.g. "Opus" with Audio and "VP8" with Video), Video resolution (e.g. 640x480), consumed bandwidth in kilobit per second (kb/s), Jitter buffer in milliseconds (ms), Round-Trip-Time "RTT" in milliseconds (how long the signal takes forth and back) and the calculated available bandwidth for Audio- and Video signals (mostly not fully consumed). The "ICE (TURN/STUN) Info" contains information about the IP-addresses and ports of the current media connection. Along with the IP-address, the connection type of the ICE candidates is displayed in parentheses ("host" - local IP in the LAN, "srflx" and "prflx" – usually publically available IP in the WAN (STUN), "relay" – usually publically available IP in the WAN (TURN)). The media connection status is shown next to the triangle bar symbol (e.g. connected). To the right the elapsed time for the Audio/VideoChat counts up.
- 
Mute button for Audio/Video devices
 Near the red *Hang-up* button a small triangle button opens a menu for "muting" the microphone or the camera devices (if present).
- 
Microphone mute overlay button with VideoChat
 In the small, local Video picture an overlay button to mute the microphone appears while moving over with the mouse. While being muted the overlay button appears striked out. Pressing again the button turns back to normal.
- 
Camera mute overlay button with VideoChat
 In the small, local Video picture an overlay button to mute the camera appears while moving over with the mouse. While being muted the overlay button appears striked out. Pressing again the button turns back to normal.
- 
Adapt Video picture size with VideoChat
 In the main Video picture an overlay button to adapt the main Video size appears (to remove black stripes) while moving over with the mouse. Pressing the button again the Video size turns back to normal.
- 
Control the remote Camera with VideoChat
 If the remote camera supports remote control and if the remote user enabled the feature with the Audio/Video Wizard the local user can move the remote camera. The camera can be turned to the left (arrow key left), to the right (arrow key right), upwards (arrow key up) and downwards (arrow key down). Further it is possible to zoom-in (key "-") and to zoom-out (key "+"). The controlling user may also move the remote camera by using the mouse in the main Video picture with the related overlay buttons.
- 
Share screen
 By pressing the Share screen button a local screen can be shared with a remote contact. The feature is available only if the related rights are granted by the administrator.
- 
Request Screen Sharing
 Would you like to see another user's screen, you can also request to share the screen by clicking Request Screen Sharing. The feature is available only if the related rights are granted by the administrator.
- Change devices**
 In an active Audio/VideoChat you can change your input/output devices here.



The configuration of your Audio/Video devices to be used with Audio/VideoChat can be done with the

	Audio/Video Wizard.
	The conversation window of a Audio-VideoChat includes also a Text Chat capability.

5.5.7 Screen Sharing

To enhance cooperation with estos ProCall Attendant Console you can share your screen with other ProCall Attendant Console users. So that the other user can see your screen content and control your mouse and keyboard once you have activated it.

Screen Sharing can be started from the context menu of an ActiveContact. The context menu is opened by a right-click on the ActiveContact. The feature is available only if the related rights are granted by the administrator. Further the Screen Sharing can be added to an existing chat in the Chat window or while an Audio/VideoChat. More further a Screen Sharing session can be started from the Contact details.

If you are sharing your screen to another party, a small "Active Screen Sharing" status window appears. Clicking on the status window moves closed or minimized conversation windows back to the foreground.

5.5.7.1 *Share a local screen with another user*

If you have shared your screen with another user a conversation window is opened showing the connected user. At the beginning of a Screen Sharing session the remote control per mouse and keyboard is deactivated. The remote control per mouse and keyboard can be activated by clicking on the "Allow control" button. It can be disabled by clicking on the button toggled as "Disable control" button. If the conversation window is closed but a Screen Sharing session is still active a small "Active Screen Sharing" status window still remembers about its activity.

5.5.7.2 *Request Screen Sharing*

Would you like to see another user's screen, you can also request to share the screen. The other party must confirm or reject to share it. The remote control per mouse and keyboard can be enabled with the "Allow control" button and it can be disabled with the "Revoke control" button.

5.5.7.3 *Select a screen for Screen Sharing*

If more than one screen exists in a system, a menu for the "Share screen" button can be opened in a conversation window, making it possible for you to select the local screen to be shared, based on a preview image. If no screen is selected or if only one screen is available, the main screen will be used. In order to ensure the privacy of the remote user, preview images are not displayed during screen share requests.

5.5.7.4 *Using Audio-/VideoChat while running a Screen Sharing session*

While a Screen Sharing session is already running an AudioChat can be added to the conversation. A camera video stream can be added to the AudioChat by opening the small menu near the "Hang up" button by selecting "Camera on". Also while an Audio/VideoChat is already running a Screen Sharing session can be added to the conversation. The upper big red "Hang up" button disconnects the entire session. The "Revoke Screen Sharing" button ends the Screen Sharing session only.

5.5.7.5 *Full screen mode*

If a user shared a screen with you the screen appears initially in a conversation window. If you maximize the conversation window you can see the session in full screen mode. If you move the mouse to the middle of the

upper screen border a window bar appears including further control buttons e.g. to end the full screen mode. The full screen mode can also be terminated with the Escape key.

➔	To use the Screen Sharing, this feature must be available on the computers of both participants.
➔	Screen Sharing is also possible for SIP federated ProCall Attendant Console users across network borders. The feature is available only if the related rights are granted by the administrator and if it is supported by the product versions on both sides. Requesting Screen Sharing between federated users is not supported for security reasons.
➔	An administrator UAC (User Account Control) prompt per Screen Sharing is not supported. Applications started with UAC as administrator can't be used within a Screen Sharing session.

5.5.8 Set up voicemail box

If a Voice Services telephone system is in use in your company, an answering machine is available. You can set up call forwarding to this voicemail box directly via the context menu on your line. A message left by the caller will be delivered to you as an e-mail.

You can set up your voicemail box via the phone using the ... menu in the estos ProCall Attendant Console main window.

The telephone menu provides you with the following options:

Main menu

You hear an announcement: You have x/no new messages

- Press 2 to change folder
- Which folder do you want to switch to?
- Press 0 for new messages
- 1 for old messages
- Or # to cancel

- Press 3 for more options

- Press 0 for mailbox options
- Press 1 to record your greeting for when you are unavailable
- Press 2 to record your announcement for when you are busy
- Or press * to return to the main menu
- Press * for help or # to exit

6 Customise estos ProCall Attendant Console

estos ProCall Attendant Console functions can be customised to your needs in many places. The first is the **settings** dialog, which you can access via the main menu.

The dialog is divided into the following categories:

- Appearance and behavior
- Telephony
- Search
- Integration
- Collaboration

6.1 Appearance and behavior

In this category you can customize the view of the client, control the behavior in certain events, assign hotkeys and shortcuts, add locations and use advanced service functions.

- View
- Characteristics
- Actions
- Action filter
- Action fields
- User-defined actions
- Hotkeys
- Shortcuts
- Location
- Advanced
- Customize dialogs with templates
- Control functions via Windows® Registry

6.1.1 View

6.1.1.1 *Presence icons*

The Presence icons in the client represent the status of the estos ProCall Attendant Console user.



Normally you always use the default symbol set. However, your administrator can provide own symbol sets to you.

6.1.1.2 *Element width*

The contacts in the Favorites tab are displayed in columns if the window width permits. With the "Element width" option you can influence as from which width a further column or a column less is displayed. Please note that the entire available window width is always used.

6.1.1.3 *Level of detail*

There are 3 levels available:




Low	This is the most compact setting, displays just the color of the presence and the name of the contact in one line.
Medium	At this stage, the corresponding contact picture (if available) for each contact and CTI information is displayed (phone lines, Calls, diversions).
High	Compared to the "Medium" level, just with larger Contact images and additionally the position in the company.

6.1.1.4 *Deposited contact with presence color*

If this option is enabled, any connected contact in the favorites is shown with its current presence color. The background of undeclared contacts remains unchanged.

6.1.1.5 *Additional lines*

The additional lines will be configured by the administrator on the estos UCServer. Normally these lines do not have an explicit owner but should be monitored and controlled by estos ProCall Attendant Console users, like a phone line in the warehouse of the company. You can still decide for yourself whether you wish to display these lines or not. If you activate this option, the additional lines are displayed in a separate sub-group on the Favourites tab. Please note that this sub-group is fixed and cannot be edited.

	The line group is automatically updated if the administrator configures it accordingly.
	To edit the line group, a new sub-group must be created and all elements of the line group copied there. Afterwards, the option Additional lines can be deactivated. Please note that the line group is no longer automatically updated if the administrator adds or removes lines.
	Changes to the settings on this page have an immediate effect on estos ProCall Attendant Console (preview). These settings are, however, only stored when confirmed with OK .

6.1.2 **Characteristics**

6.1.2.1 *General*

Display estos ProCall Attendant Console with Windows® log-on

Use this option if estos ProCall Attendant Console is to be started automatically when the system re-boots. The client is always started minimised in this case.

Show start process

Check this checkbox if you want more detailed information to be shown on the screen when estos ProCall Attendant Console starts.

6.1.2.2 *Show speech bubble for*

If at least one of these settings are active a speech bubble will show you the according information near the windows taskbar.

- **Unread E-Mails**
Display of new e-mails in the in-box

- **Chats**
Display of unanswered chats
- **Planned calls**
Display of planned calls due
- **Challenge-Response**
Display of open Challenge-Responses
- **Fax messages**
Display of new Fax messages in the Inbox

6.1.2.3 *Advanced*

- **Open Contacts by default for editing**
Contacts are normally opened for display in estos ProCall Attendant Console. Alternatively, you can set-up the contacts to be always open for editing. By keeping the CONTROL key pressed down, you can switch to the operation not selected by default when clicking on a contact.
- **Commit contact detail tabs last selected to memory**
With this function, you will open the contact detail window always with in the same tab. If you close the contact detail window in the tab "Unprocessed", the page "Unprocessed" will automatically appear when you next open a contact.
- **Register as default telephony application**
Here you can control whether estos ProCall Attendant Console should automatically register itself automatically at start as a standard-telephony application. The standard-telephony application takes on telephone dialing requests on the TAPI level and diverts this to the telephone or telephone system.
- **Register as default Instant-Messaging application**
This lets you control whether estos ProCall Attendant Console is to automatically register at start as a default application for instant messaging. The default application for instant messaging is for example used by Microsoft Outlook® to start chats or to get contact information such as presence, contact name or contact picture.
- **Play notification sounds**
Notification sounds of estos ProCall Attendant Console will be configured through the audio scheme of Microsoft® Windows®. You can switch off notification sounds altogether here and open the relevant Windows® settings page.

6.1.3 **Actions**

Automate estos ProCall Attendant Console:

estos ProCall Attendant Console enables you to execute numerous of actions if defined events occur (ringing phone for example). The following tabel givs you a brief overview:

Event	Description
In case of an incoming call	Occurs when your phone rings.
In case of an outgoing call	Occurs, when you have established a call and the phone rings with your respondent.
At the end of a call	Occurs when the call (not connected) or the conversation (connected) was ended.
When call is answered	Occurs when you accept an incoming call or your dialog partner accepts an your

	call.
When the remote call party changes	Occurs when the dialog partner changes during the call.
After logging on to the server	Occurs when the user could log on estos UCServer successful.
After logging off from the server	Occurs when estos ProCall Attendant Console properly log off from the server. This is particularly the case when estos ProCall Attendant Console shuts down, but not when the compound is separated from the estos UCServer.
In case of an appointment (busy)	Occurs when an appointment in Outlook® which is marked with the "busy" attribute becomes due.
In case of appointment (out of office)	Occurs when an appointment in Outlook® which is marked with the "absent" attribute becomes due.
Automatically opened contact detail window	Occurs when a contact details window open by estos ProCall Attendant Console automatically.
After xx minutes idling	Occurs, when you have pressed no key or moved your mouse in xx minutes.

6.1.3.1 **Create new action:**

1. Click **Add new action** and select the event when the action is to be executed in future.
2. Click **Choose action** and select the action which is to be executed by the selected event.
3. Make sure that the checkbox to the left of the selected event is active (checked). The action will only then be executed. You can also uncheck the checkbox if the action should not to be performed at present but will be needed later.

6.1.3.2 **Activate/deactivate action**


You can create an action for later use or temporarily deactivate an already created action if you deselect the hook on the left, beside the event field. As soon as the hook is input again, the event happens.

6.1.3.3 **Remove actions**

Actions which are no longer required can be removed with the "Delete" button at any time. The action to be removed must first be marked. Alternatively you can select the **Remove action** entry in the event field.

6.1.3.4 **Use Actions filter**

estos ProCall Attendant Console allows you to limit certain events by the aid of action filters, or to describe something more specifically. To put in an Action filter or to change, click on the filter button in the suitable row.

-  Up until now no Action filter was defined or the Action filters were deactivated. Click on this button to apply an Action filter or to activate the Action filter.





-  An action filter was defined and activated. Click on this button to change the Action filter or to deactivate the Action filter.

You can find further information in the section Action filter.

6.1.3.5 User-defined actions

estos ProCall Attendant Console gives you the option to create actions by yourself. These can be additionally selected when an event in the action list occurs. To create a new action, click the "Actions" button.

An overview page opens with all actions that have already been defined. For each action, you have the option of specifying there whether it is to be displayed in the main menu or in the context menus You can find more information about this in the section User-defined actions.

	The events "at appointment (engaged)" and "at appointment (absent)" work only if data should be transferred, what can be changed by the settings under calendar.
	A call diversion which is preset "at appointment (busy)" or "at appointment (absent)" as an action in the events, is also set as not activated in estos ProCall Attendant Console.
	A call diversion which is preset "at appointment (busy)" or "at appointment (absent)" as an action in the events, is reset at the end of the appointment again.
	If no actions have been defined to an event this entry is deleted when the settings dialog is closed.

6.1.4 Action filter

Action fields are rules that describe the execution conditions of the action or of the event in greater detail. Thus you can specify to execute or be able to execute actions only in specified cases. The action will only be executed if *all* input rules apply.

Set the check mark to **use filter** in order to create a filter. Remove the check if you want to disable an already defined filter, however it is not deleted immediately.


Click on the button **Add...** and choose the field name whose field value should fulfil a condition. Here you are offered every action fields.

After you have chosen the field name, enter the rule in the column **Regular expression** which the field value must fulfil.

6.1.4.1 Regular expressions




A brief overview of the permitted expressions:

Character	Description
^	The beginning of the string. With the Caret at the beginning of the regular expression, it is determined that the field value must agree from the outset. The expression "^o " means that the field value must begin with "o ".

^	The caret (^) directly after the left bracket ([) has another meaning. It is used to exclude the other signs within the bracket. The expression "[^0-4]" permits only figures except 0 to 4.
\$	The dollar character (\$) calls the end of the string. The expression "152\$" is valid only for strings which end with "152".
	The sign () permits both characters between it. The expression "8 9" permits "8" or "9".
.	The point (.) permits every character (or every figure).
*	The Star (*) indicates, that the character to the left must exist 0 times or more.
+	The Plus (+) is similar to the Star, only that the character to the left must exist at least 1 time.
?	The question mark (?) indicates, that the character to the left must exist 0 or 1 time.
[]	The corner brackets ([and]) indicate the amount of characters that are permitted at this point.
\	The Backslash is used as an Escape sequence. If you want to search for "+", you must write "\+".
	Tip: The Caret sign (^) can be found on the top left of a German keyboard.

6.1.4.2 Check filter

You can check your input immediately here. Enter a value as an example in the field of the same name. The example value is applied to all regular expressions. The symbols beside the field name indicate whether the example value on the regular expression fits.

-  The blue symbol indicates that either no example value was entered, or that the entered example value does not fit on the regular expression.
-  The green symbol indicates that the entered example value on the regular expression fits.
-  The red symbol indicates that the regular expression is not valid. In this case correct the regular expression.

6.1.4.3 Examples

Effect	Actions field	Regular expression
Complete only with internal calls	<Call.Internal>	1
Complete only with external calls	<Call.Internal>	0
Complete only with calls from Germany	<Call.NumberSC>	^\+49
Complete only with calls from Germany or Switzerland	<Call.NumberSC>	^\+49 ^\+41

Complete with calls, in which no contact was found	<Call.ContactEntryID>	^\$
Execute only with contacts of the company "estos GmbH "	<Contact.Company>	^XYZ GmbH\$
Complete only with high priority appointments	<Appointment.Importance>	2
Run only for appointments that start at 9 clock (german date format)	<Appointment.StartTime>	09:00
Run only if appointments start at 9 o'clock (American date format)	<Appointment.StartTime>	9:00:00 AM

➔ Filters can be used both to limit a specified event, and also to determine the basic conditions for user-defined actions of when a user-defined action makes sense. Dependent on this, set the filter for a specified entry in the Event/Action list or in the user-defined actions yourself.

➔ Please note that in certain events not all fields can be used. Thus no appointment fields are available, e.g. for telephony events. An entire overview of all fields, as well as which fields are available with which events, can be found in the section action fields.

➔ Action fields that represent a timestamp, such as <Appointment.StartTime> use the date format configured for the local computer. This corresponds to the display of dates, as estos ProCall Attendant Console displays them in the log view in the Date column. For example, "Mo 02.07.2012 15:10:25" (Germany) or "Mon 7/2/2012 3:10:25 PM" (USA). The Date column can be added to the column headers on the **Journal** tab page by right-clicking the column header with the mouse.

6.1.5 Action fields

While editing User-defined actions in estos ProCall Attendant Console you can use placeholders which were replaced when the action is executed with actual data (e.g. the phone number of the participant in the discussion will be filled in). These placeholders can also be used for action filters.

The Action fields can be divided into three different groups:

- Telephony-Action fields
- Contact-Action fields
- Appointment-Action fields

6.1.5.1 Telephony-Action fields

Field name	Description
<Call.NumberSC>	The phone number in supercanonical format (e.g. +49301234567)
<Call.ContactEntryID>	The database or Outlook® EntryID of the contact, if one was found.

<Call.ContactEntryIDStore>	The database or Outlook® EntryID of the Messagestore in which the contact was found
<Call.ContactEntryDDB>	The database identifier of the database in which the contact was found.
<Call.ContactName>	The display name of the contact, if a contact was found for the phone call.
<Call.Origin>	The direction of the phone call: 1 for "outgoing", all other values mean "incoming".
<Call.Internal>	Indicates whether the call is internal or external: "1" for internal, "0" for external.
<Call.Private>	Indicates whether the call is marked as private: "1" with private calls.
<Call.ProjectName>	The project name, if the telephone call is assigned to a project.
<Call.ProjectPIN>	The project PIN, if the telephone call is assigned to a project.
<Call.Note>	Contains the call memo.
<Call.LineNumberSC>	Own extension number in canonical format.
<Call.LocalNumberSC>	The phone number called for incoming calls. The line number for outgoing calls.
<Call.LocalNumberName>	For activated hotline services (client function) the contact found for the LocalNumberSC
<Call.RedirectingSC>	The forwarding phone number in canonical format.
<Call.RedirectingName>	The name of the contact who forwarded the call.
<Call.HoldNumberSC>	The number of the contact that is being on hold.
<Call.CreatedTime>	The time at which the call has been created on the server.
<Call.ConnectedTime>	The time at which the call was accepted.
<Call.DisconnectedTime>	The time at which the call has been terminated.

6.1.5.2 Contact-Action fields

Field name	Description
------------	-------------

<Contact.DatabaseName>	Readable name of the database which the contact comes from.
<Contact.EntryID>	The database or Outlook® EntryID of contact.
<Contact.EntryIDStore>	The database or Outlook® EntryID of the messagestore, in which the contact was stored
<Contact.EntryIDDB>	The Database identifier of the database, in which the contact is stored
<Contact.CtiServerUserName>	The CTI username if it is a CTI user
<Contact.DisplayName>	The contact's display name.
<Contact.FirstName>	The contact's first name.
<Contact.LastName>	The contact's last name.
<Contact.JobTitle>	The contact's job title.
<Contact.Company>	The contact's company name.
<Contact.Department>	The contact's department.
<Contact.OfficeRoomNumber>	The contact's office number.
<Contact.CustomerID>	The contact's customer number.
<Contact.BusinessAddressStreet>	The street of the contact's company address.
<Contact.BusinessAddressPostalCode>	The Post code (zip code) of the contact's company address.
<Contact.BusinessAddressCity>	The town/city of the contact's company address.
<Contact.BusinessAddressState>	The province/state of the contact's company address.
<Contact.BusinessAddressCountry>	The country of the contact's company address.
<Contact.PrivateAddressStreet>	The street of the contact's private address.
<Contact.PrivateAddressPostalCode>	The Post code (zip code) of the contact's private address.
<Contact.PrivateAddressCity>	The town/city of the contact's private address.

<Contact.PrivateAddressState>	The province/state of the contact's private address.
<Contact.PrivateAddressCountry>	The country of the contact's private address.
<Contact.OtherAddressStreet>	The street of the additional contact's address.
<Contact.OtherAddressPostalCode>	The post code (zip code) of the additional contact's address.
<Contact.OtherAddressCity>	The town/city of the additional contact's address.
<Contact.OtherAddressState>	The province/state of the additional contact's address.
<Contact.OtherAddressCountry>	The country of the additional contact's address.
<Contact.EMail>	The contact's first e-mail address.
<Contact.EMail2>	The contact's second e-mail address.
<Contact.EMail3>	The contact's third e-mail address.
<Contact.SIPAddress>	The contact's SIP-Address (or instant messaging address).
<Contact.WebPageURL>	The contact's Web-Address.
<Contact.PhoneBusiness>	The contact's first business phone number.
<Contact.PhoneBusiness2>	The contact's second business phone number.
<Contact.CompanyMainTelephoneNumber>	The contact's company phone number.
<Contact.AssistantTelephoneNumber>	The contact's assistance phone number.
<Contact.PhoneHome>	The contact's first private phone number.
<Contact.PhoneHome2>	The contact's second private phone number.
<Contact.PrimaryTelephoneNumber>	The contact's primary phone number.
<Contact.PhoneMobile>	The contact's mobile/cell phone number.
<Contact.CarTelephoneNumber>	The contact's car telephone number.
<Contact.RadioTelephoneNumber>	The contact's radio phone number.

<Contact.PagerTelephoneNumber>	The contact's pager phone number.
<Contact.OtherTelephoneNumber>	The contact's additional phone numbers.
<Contact.CallbackTelephoneNumber>	The contact's callback phone number.
<Contact.ISDNTelephoneNumber>	The contact's ISDN phone number.
<Contact.TTYTTDTelephoneNumber>	The contact's hearing impaired phone number.
<Contact.FaxBusiness>	The contact's business Fax number.
<Contact.FaxHome>	The contact's private Fax number.
<Contact.Body>	The contact's memo text
<Contact.IsPrivateContact>	Indicates whether it is a private or business contact.
<Contact.IsCtiServerUser>	Indicates whether it is a CTI-user.
<Contact.DirectWebLink>	The contact's Web application link for web-based CRM systems.
<Contact.Custom0> - <Contact.Custom19>	Contents of the custom contact fields "Custom0" to "Custom19".


6.1.5.3 Appointment-Action fields

Field name	Description
<Appointment.EntryID>	The database or Outlook® EntryID of the appointment.
<Appointment.OwnerName>	The owner of the appointment.
<Appointment.DataSource>	The database identifier of the database, in which the appointment is stored.
<Appointment.StartTime>	The date and time the appointment starts.
<Appointment.EndTime>	The date and time the appointment ends.
<Appointment.Duration>	The duration of the appointment.
<Appointment.Subject>	The subject of the appointment.

<Appointment.Body>	The memo text of the appointment.
<Appointment.AllDay>	Indicates whether it is an all-day appointment.
<Appointment.Status>	Indicates the status of the appointment.
<Appointment.Category>	The category of the appointment.
<Appointment.Importance>	The level of importance of the appointment.
<Appointment.Sensitivity>	The level of confidentiality of the appointment.

6.1.5.4 Event dependend

Depending on the event, for which a User defined action or a Actionsfilter is created, different Action fields can be used:

Event	Available Action fields
On incoming call On outgoing call At the end of a call When call is answered When the remote call party changes	Telephony-Action fields Contact-Action fields
In case of an appointment (busy) In case of appointment (out of office)	Appointment-Action fields
Automatically opened contact detail window	Contact-Action fields
After xx minutes idling When computer is locked	-
 Please note also that not all fields can be combined with one another. For example, a user-defined action cannot simultaneously have a reference to telephony action fields and appointment action fields.	

6.1.6 User-defined actions

User-defined actions serve to implement programmes with certain phone call actions. Some information can be transferred at the start of the programme as a command line. In most cases it will concern applications developed yourself which carry out additional functions, e.g. when a phone call is signalled.

Overview list of the user-defined actions

All configured actions will be displayed in the Overview list. You can add new actions or edit existing actions or delete them again. In addition, for each action you can determine whether it is offered in the Main menu or in the context menus and/or in the dialog box, to then be able to execute it manually if necessary:

Filter

The filter can be used in the user-defined actions, in case the execution of the action only makes sense under certain conditions. For example, the user-defined action might only be practical for selected contacts from specified data sources or for specified conversation states. With a set filter the action will only be offered when the conditions defined there apply. You will find examples of filters in the section Action filters.

Menu integration

Any user-defined action can also be integrated in the menus of the client. Hence, the action can also be implemented without a special event. Depending on the set filter or depending on the Action fields used there, the action will be offered in the corresponding menus. For example, if you specified a contact field, the action will only be used in menus with a contact reference, thus in the context menus of the contacts, but also in the context menu of a journal entry with a contact reference. Without a filter the action is always executable and is thus offered in the Main menu.

Call window integration

In addition to or as an alternative to menu integration, the action can also be incorporated in the Call window as a button. To do this, enable the checkmark in the Overview list of the user-defined actions.

Set up a user-defined action

Any user-defined action is defined by the following specifications:

Action name

Allocate a name here, which is indicated. This name is for your information only and is recorded on the list of available actions on the settings page Behavior.

Application

Give the path for the application which you want to complete here. You can also specify the document to be opened. In addition, specific field names which are replaced at Program start with the corresponding values of the phone call, contact or appointment, can be entered here. You can find an overview in the section action fields.

Command line

Give here which command line of the program should be transferred. As with the application line, the given fields which are replaced by Program start with the corresponding values of the phone call, contact or appointment, can be used here. You can find an overview in the section action fields.

Directory

The list in use should be begun.

Mode

Here you can state how the program should start (maximised, minimised, normal or hidden). Not every program evaluates this parameter!

Description

This is a free text which is displayed in the tool tip of the action in the conversation window integration.

Change icon

Here you can determine the icon that should be used in the menu integration or conversation window integration for this action.

Example:

It should be a user-defined action which opens the homepage of the caller automatically.

1. Give the action a descriptive name, e.g. "web page open".
2. Enter in the application line, the entire path to your Internet browser, e.g. "C:\programFiles (x86)\Mozilla Firefox\firefox.exe".



3. As a parameter, the browser expects the URL of the Internet site to be opened. The URL is restored by estos ProCall Attendant Console in the contact-action field "WebPageURL ". Enter in the command line of the field names "< Contact. WebPageURL>" or click on "field add" and select the entry of the same name from the list.
4. You do not have to state the complete list. Simply leave the line "list" free.
5. Because the browser with the homepage should be indicated, set the mode to "Normal start".

6.1.7 Hotkeys

The term hotkey describes the option of defining system-wide key combinations which permit phone numbers to be dialed or calls to be ended (hang up) out of almost all programs. You define the key combination in this settings dialog.

Dial selected phone number, otherwise start Contact Search.

To dial a number with the shortcut key, the number has to be selected with mouse in the according window, then press the shortcut key. If there is no phone number selected, estos ProCall Attendant Console tries to search for a contact instead.

	You can use the hotkey in Outlook® itself. You can thus dial any phone number in a contact by marking the phone number. Use the hotkey also to transfer a contact to the phone status window. You can also start callback from the journal with the hotkey.
	Dialing from a console application (DOS window): If the phone number cannot be selected directly by the mouse, then first activate the DOS Console's Editing Mode using [ALT]+[Spacebar].

Use this hotkey also for accepting a call




If this option is selected, incoming calls can be answered with the same hotkey as is used for dialing (if your phone supports this feature).

Shortcut key for hanging up

Here you can define the hotkey for ending the active connection. Type in the key combination (special keys such as Alt, CTRL and Shift are also possible). You delete the hotkey with the Del key.

Display main window

This Hotkey brings the main window of estos ProCall Attendant Console on screen and you can immediately start searching contacts.

	These hotkeys are configured system wide, so no other application can use the same key combinations for other actions.
	Dialing with the hotkey uses the Windows® clipboard and the keyboard shortcut [CTRL+C]. The contents of the clipboard can be changed at the same time and the shortcut [CTRL+C] not used as a hotkey. Consider these restrictions with the use of this function.
	Phone numbers or contacts cannot be dialed (or searched) from applications that have been started with higher administration rights than estos ProCall Attendant Console. If the hotkey has been pressed in such an application, an information dialog will provide a reminder. estos ProCall Attendant Console can only display this reminder if the hotkey is used in combination with or (a Windows® restriction).



If phone numbers cannot be dialed, advanced users can attempt to give the other applications more time so that this data can be provided. See Function control via Windows® Registry for more information.

6.1.8 Shortcuts

To increase productivity, certain application features can be assigned to key shortcuts. Thereby, certain tasks and features can be started, opened or executed using a simple shortcut.

The list contains all available features, sorted by units, that can be assigned to shortcuts.

Assign a shortcut to a feature:

Click on the second column so that a text entry cursor will appear. Then simply press the desired key combination.

Delete a shortcut:

The Delete button can be used for this purpose. If you are currently in the process of assigning a new key, simply press [Del].

Reset all shortcuts to their default values:

The two buttons "Reset" and "Reset All" are available for this purpose.



The shortcuts for features that have been grayed out cannot be modified. This can be because of the following reasons:

1. The shortcuts may have been assigned by the manufacturer.
2. The shortcut has been assigned by the System Administrator using group policies.



If a conflict is discovered between the chosen hotkey and a hotkey from another application, an alternative hotkey should be chosen, or remove the other hotkey from the other application first.

6.1.9 Location

Location settings contain all the necessary information which make it possible for phone numbers to be correctly dialed and displayed. These settings are especially important if you are using a phone system or if your phone is attached to a phone system, otherwise external numbers could not be dialed and the displaying a phone number would not function correctly.

The country, dialing code and phone or phone system settings are configured exclusively in estos UCServer and cannot therefore be changed in the client. If you have more than one line assigned, the Location settings always refer to the selected default line.

You can configure in which format the phone numbers should be shown in estos ProCall Attendant Console. Internal phone numbers will always be shown in short notation.

Address

You should enter your location's address here. This information is necessary and is used exclusively for the map function and route planning.

Map/route planning

Select a service from the list which you wish to use for the map function and route planning. You can choose the language in which the route information is displayed.

➔	If no country name was indicated in a Contact, the country name of your default location will be assumed.
⚠	To plan a route to a contact it is important that a complete address is available for the contact.
⚠	The name of the country in a Contact must be spelled in full. A "D" or "de" for Germany is not enough. The name of the country may be given in several languages such as, among others, German, English, French or Japanese.

6.2 Location

Location settings make it possible for phone numbers to be correctly dialed and displayed.

Only with the correct Location settings it is possible to ensure that external phone numbers can be dialed correctly and phone numbers are displayed properly.

This section of the help file will describe the individual configuration parameters on the Location Settings dialog. If a location is depicted, the following pages will provide all information necessary for configuration. If several networked locations must be setup, all information for special configuration scenarios can be found in the Location Designs section.

Country/region:

Choose your country from this list.

Area code

Enter your local area dialing code here. This is for example 030 for Berlin or 44 for Zurich (Switzerland). The leading 0 is not necessary and is removed by the system when the settings are saved.

Display Advanced Settings

The location settings have many options that will only be needed in special cases. Settings that are not mandatory for normal operation will not be displayed by the wizard.

The advanced settings include:

- Rules for the detection of internal and external phone numbers
- Rules for formatting the line phone numbers
- Special formatting of phone numbers that will be registered by the telephone system
- Special formatting of phone numbers that will be transferred to the telephone system for dialing
- Least cost routing
- Vanity phone numbers

6.2.1.1 Formatting

These rules apply to phone numbers reported by the TAPI driver of the phone system.

You can enter several extension numbers, separated by commas, in all fields. Normally the extension numbers are identical (default value: 0).

Remove access codes for outside lines for phone numbers

- **reported as incoming:**
Enter the extension numbers to be deleted from the phone number in case of incoming calls.
- **reported as outgoing:**
Enter the extension numbers to be deleted from the phone number in case of outgoing calls.
- **reported as a forwarded call:**
Enter the extension numbers which must be removed from the phone number in case of forwarded calls.

Remove codes for outside lines for the ConnectedID

- **reported as incoming**
Enter the extension numbers which should be removed from the number for incoming connected calls.
- **reported as outgoing**
Enter the extension numbers which should be removed from the number for outgoing connected calls.
- **Ignore ConnectedID**
If the driver for the telephone system reports inconsistent number formats for ConnectedID (different forms of numbers to get an outside line for incoming, outgoing or connected calls), you must ignore the ConnectedID. As a result, you will not see the actual number of the person at the other end, but only the number of the person called or calling.
This option is the last chance to catch inconsistent numbers from the driver. Please try first to make the reported numbers consistent by configuring the driver or the telephone system. **Only activate this feature when it is absolutely necessary.**

6.2.1.2 *Dialing prefixes*

Outgoing PC dialing:

An external access prefix (also referred as external dialing code) is the number on the telephone that must be used to make an external call. The entry of this number will be required for dialing from ProCall even for automatic external access on the telephone. Normally, the following external dialing codes are identical (default value: 0).

- **Local access code:**
Enter the access code you need for calls to destinations in your own area.
- **National access code:**
Enter the access code you need for calls to national destinations.
- **International access code:**
Enter the access code you need for calls to international destinations.
- **Private call external dialing code:**
Enter the access code required for placing external phone calls. The placeholders: e, E, u or U (see Projects); may also be used.
- **Number for an outside line required to activate call forwarding:**
Here, enter the number for an outside line which you require for call forwarding.

Determine external access prefix...

The wizard will provide support in determining the external access prefix (also known as "external dialing code", "trunk access code" or "outside line access code"). Access to a telephone at the location and an external telephone (cell phone) will be needed. If there is uncertainty about the external dialing code, start the wizard and follow its instructions. All settings for the external dialing code will be set automatically.

6.2.2 Advanced

Core services

Phone number format, PC dialing

This option determines the phone number format for outgoing calls. Phone numbers are transferred in this format to the phone system.

- Apply dialing rules (standard)
Phone numbers are always formatted according to the dialing rules.
- Always international super-canonical/E164
Phone numbers are always converted into the super-canonical phone number format (e.g. +1891234567, also known as international E.164 format) before they are sent to the phone system. Only activate this option, if your phone system and the TAPI driver supports this phone number format.

Always enter the area code for local phone numbers.

If the area code must be dialed for calls in the local area, this option must be enabled. In some cases, IP Centrix providers require the call to be dialed with the corresponding area code.

Automatically re-dialing extensions

If a number to be dialed is longer than the maximum phone number length allowed in the corresponding target country, the number will be divided into sections and the first section dialed and then the remaining section dialed as a DTMF number after the connection has been made. This currently applies for countries like the United States, Russia and Taiwan. The maximum phone number length is defined in the countries.xml and cities.xml files. If the option has been deactivated, the telephone system will have to emulate this behavior.

Abbreviate Phone Numbers before Dialing

Long phone numbers from other locations will be abbreviated to the DDI phone numbers before dialing. The rules to be determined for this will be displayed under PC Dialing. If dialing between locations requires cross-network identifiers, the rules will have to be configured manually from PC Dialing.

6.2.3 PBX system

Location is using a PBX

Activate this option, if the location has a telephone system.

Public line type

Please select the type of the public line: DDI trunk line (for Direct Dial-In) or a Multipoint connection line. Sometimes DDI lines are also referred to as DID lines (for Direct Inward Dialing). A DDI line enables external parties to call internal phones directly using phone number ranges. DDI numbers comprise of a PBX base number (addressing the PBX) plus a number range (or several ranges) to address internal phones from outside. A Multipoint connection typically is used for smaller offices or for home usage. One or more phone numbers (Multi Subscriber Number = MSN) are used in this case. The MSNs may be totally different, e.g. they don't have to use numbering ranges.

PBX base number (only with a PBX using a DDI line)

If you have a DDI line you should enter the PBX base number here. For example if you have the number +1 (30) 12345-222, the PBX base number is 12345.

Extension Numbers (DDI - Direct Dialing In) (only with a PBX using a DDI line)

If all extension numbers have the same length configure an extension number space. If extensions are used with different lengths configure extension number prefix.

Extension number space

Please enter here the extension number range (DDI range or space) that is allocated by the phone company for the related PBX. For example, if you have the DDI number range from +1 30 12345 30 to +1 30 12345 69, enter "from 30 to 69". Or for example using three-digit extensions while the entire range is available for DDI enter "from 100 to 999".

All internal phone numbers available in this range are displayed automatically as external, international phone

numbers.

Extension number prefix

Please specify the lowest and the highest first digit of the extension numbers. If e.g. the internal numbers 20, 300-499 and 5000 are used please configure '2' as the first prefix and '5' as the second prefix. The length of the internal numbers are set to '2' to '4' in this case. Depending on the length of the internal numbers the program calculates the numbers to be used as external and international types.

Length of internal phone numbers:

Enter the length of longest and shortest internal phone numbers. If all extensions are the same length, for example 121 (three digits), both entries should be "3".

Extension phone number format:

External phone numbers: displays the international phone number for the location (only for a system connection).

Internal phone numbers: displays the internal phone numbers for the location

6.2.4 Least cost routing

Least cost routing is the automatic selection of the cheapest call-by-call provider for a call. You must configure rules in order to make this choice for a call. For the ProCall Attendant Console LCR to be able to offer LCR, there have to be rules setup. These kann be setup manually oder implemented from different web services.

Information about current rates of Call-by-Call providers can be found on the internet under www.estos.de/produkte/unified-communications/procall4plusenterprise/lcr.html.

- **Provider**
The Provider list will contain all stored Call-by-Call providers with their respective dialing codes.
- **Zones**
The Zones list will contain the zones for the Least Cost Routing feature.
- **Assignment of zones to providers**
Through the Allocation of providers, the system will know when to use which provider. In addition to differentiation based on the day (Monday-Friday, Saturday & Sunday), the providers may be allocated to the configured zones based on time

Reset

Deletes all LCR settings.

Import and export

You can import and export all LCR settings. The following formats are supported:

- Own LCR-data format (*.lcrxml)
- Agfeo LCR-data format (*.lcr)
For Germany you can obtain LCR-data in this format from several providers in the Internet.

6.2.4.1 Least cost routing assignment

Every zone can be assigned to a provider. This assignment is separate for Monday to Friday, Saturday and Sunday. Different providers can be used at different times for each of these days.

The time (in 48 half-hours) is plotted to the right of the table. The configured zones are listed at the bottom. Each line of the table shows which provider is used for the zone at the respective time.

Select the provider which you wish to assign. Next, click on the cells date and time in the table where the provider is to be used.

6.2.4.2 Provider

A provider is a provider of call-by-call telecommunications services. In order to use a provider for a phone call the provider's network dialing code is dialed before the phone number.

Examples for Germany

Provider	Pre-selection network prefix
Arcor	01070
Tele2	01013

6.2.4.3 Zones

A zone represents a list of phone numbers which can be called for a certain tariff. You can assign a provider to every zone according to date and time.

Zone name

Enter a name for the zone, e.g. long distance or mobile.

Area code list

All phone numbers which start with digits provided in the list belong to this zone. The phone numbers will be compared when processing the Dialing Rules. Entries must be made in international format (such as: +49171).

Examples

Area code	Meaning
+1	All numbers which begin with +49, in other words all phone numbers in Germany (apart from special numbers).
+1905	All phone numbers which begin with +1905, in other words all numbers in Toronto, Canada.
+117	All phone numbers which begin with +4917, in other words all mobile phone numbers in Germany with a 017x dialing code.

Instructions

You typically configure zones for local calls, long-distance calls and mobile phone networks and several zones for other countries.

Priority of longer dialing codes

If there are several dialing codes configured in different zones which fit the phone number, the zone which has the greater number of digits in its dialing code is used.

Example: the number +4917123456789 is dialed. If +4917 is entered in zone 1 and +49171 in zone 2, zone 2 is used because more digits match.

Priority of zones without providers

If there are several dialing codes configured in different zones which are identical and one zone has no provider assigned to it the zone without a provider has priority.

6.2.4.4 Line phone numbers

The rules permit detection of phone numbers based on Regular Expressions or direct comparison. Each entry can be configured individually. If the Replace With column has been entered, the phone number will be replaced automatically. The phone number should be formatted using international notation after the formatting process. The configured rules will be processed from top to bottom until the first match has been found.

Check:

The rules can be checked immediately. Enter the corresponding expression in the Phone Number field. If the phone number was detected and how it has been implemented can be seen in the output row. The rule used for recognizing and formatting will be highlighted.

➔	<p>Specific Examples for the Use of Rules for Adjusting Line Phone Numbers:</p> <ul style="list-style-type: none"> • Phone Numbers with Cross-network Identifiers (Cisco) • Internal and external phone numbers outside of the base number range (lines do not carry the DDI phone numbers, but rather internal line identifiers).
➔	<p>If a comprehensive set of rules should be established, the list can be maintained outside the administrator's utility. Existing rules can be exported as XML or CSV files, adjusted correspondingly and then re-imported.</p>

6.2.5 Projects

estos UCServer permits the user to assign calls to previously defined projects, to send certain code numbers to the phone or the phone system when dialing or to mark calls explicitly as private.

Parameters are, for example, used with targeted MSN assignment, the initiation of private calls in phone systems or for dialing project parameters. You can define several parameters here and give them names. They can then be used in the call window. The parameters are always saved in the journal on the estos UCServer.

Parameters have two functions:

- Parameters for dialing. These are sent to the phone system and activate specific features before making the call.
- Parameters for the Journal. These are included in the journal (server-side) and are subsequently used for invoicing by project parameters.

Define projects:

1. Enter a readable name for the project in field **name**. This name appears later in the call window and the journal.
2. Enter the **parameter** which is dialed before the actual number in the column of the same name.

The following rules apply:

Character	Deployment
0-9 * #	Digits which are dialed normally
C	Here you wait for the remote station to accept the call.
e, E	Place-holder for entering a PIN. With E, the number of digits for entry is not important. With e, the number of digits is defined by the number of letters (eee for three digits).
u, U	Place-holder for entering a user ID. With U, the number of digits to be entered is not important. With u, the number of digits is defined by the number of letters (uuu for three figures).
p, P	Dialing pause: p for 0.5 seconds, P for 1 second
N	Place-holder for the number to be dialed. If the place-holder is not specified the number is automatically added to the end.
J	Defines, if available, that the user login and pin number entered by the user is noted in the journal.
X	Defines, if present, that the number to be dialed should be dialed with an external code. If the 'X' is missing the number is dialed in national format (03012345678).

- Select one of the following **options** which is to apply for the project:

Journal entry only: The parameter is not sent to the phone but just saved in the journal.

Dialing and journal entry: This parameter is used for outgoing dialing is saved in the journal entry.

Dial only: This parameter is only used for dialing.

Dial Private Call: The Access Code for Private Calls option is used for this (see Dialing Prefixes). Doing so may be necessary in order place private calls, depending on the telephone system and configuration. Phone numbers used for private calls will not be visible to others and will be additionally flagged in the journal.

Examples of use:

- For the journal only:
You wish to assign project parameters to calls. Create an entry and name it e.g. Project Test and give the parameter 12345. Select the Journal entry only option. The parameters are logged on the server side only.
- Selective external dialing code:
Assume you have have a normal external dialing code of 'o' and a further external dialing code which is '8o'. Create an entry and name it 'External2'. Enter '8o' as the phone number. Select the 'Dial only' option.
- Select project parameter:
Assume you can dial the project parameter '4444' on the phone with the combination *6o4444#. Create an entry and name it 'Current Project'. Enter *6o4444# as the phone number. The X means that an external dialing code must be added after the project parameter. You can then also make internal calls with this project parameter.
- Private call 1. Example:
Assuming you can dial a private call on the phone with your personal PIN '1234' by means of the combination *6o1234#: create an entry and name it 'Private'. Specify the number as *6oeeee#X. The 'X' means that an external code must follow the parameter. You can then also make internal calls with

this parameter. The 'eeee's mean that you still have to enter a four-digit PIN. If you then dial in the call window with this setting you are asked to enter this PIN. You can, of course, enter the PIN for private calls here directly, in other words *601234# (if no other person has access to your computer).

- Private call 2. Example:
Assuming you can dial a private call on the phone with your personal PIN ,1234' by means of the combination 51234: after entering the PIN you no longer have to dial an external code. Create the entry and name it 'Private'. Enter 5eeee as the phone number. This time, no X is used (no external code after the parameter). The 'eeee's mean that you still have to enter a four-digit PIN. If you then dial in the call window with this setting you will be required to enter the PIN. You can, of course, also enter the PIN for the private call directly here: 51234.
- Example of a calling card provider:
With the rules you can deal with dialing a calling card provider for private conversations. Enter the phone number format required by the calling card provider in the project parameters field.
E.g.: 0080012345678CP#eeeeeeee#uuu#N#
The calling card provider is dialed via the number 0080012345678. After the call has been answered there is a one-second delay; the 8-digit user ID and then the four-digit password is subsequently transmitted, followed by the number to be dialed. The placeholders for 'e' and 'u' were queried by the user in the client. User recognition and the PIN can be saved on the client if desired.
The subsequent dialing of digits after a pause or waiting for an answer from the remote station is realised with DTMF tones. This is only possible if your TAPI driver supports this feature.

6.2.6 Check rules

Here you can check the configured rules. Enter a phone number and check if the phone number is used correctly for displaying or dialing.

Format for dialing

Formats a phone number that will be transferred to the telephone system for dialing. The formatting process will perform the following steps:

Formatting for call forwarding

Formats a phone number that will be transferred to the telephone system for call forwarding. The formatting process will perform the following steps:

Format for display

Formats a phone number for display.

ConnectedID outgoing

Formats the outgoing ConnectedID reported by the driver. The formatting process will perform the following steps:

ConnectedID incoming

Formats the incoming ConnectedID reported by the driver. The formatting will perform the following steps.

CallerID

Formats the CallerID reported by the driver. The formatting process will perform the following steps.

CalledID

Formats the CalledID reported by the driver. The formatting process will perform the following steps.

Call forwarding

Formats the phone number for call forwarding reported by the driver. The formatting process will perform the following steps.

6.2.7 Area code rules

These settings are only required for countries in North America.

The area code rules determine which dialing rules must be used for dialing a number in the North American Numbering Plan (NANP). The number must be dialed differently depending on how far the number you wish to dial is from your own location. For example, a free call must be dialed differently to a chargeable call.

The target number to be dialed decides which dialing rules are used. The number's area code and the three digits which follow it are decisive.

Own area code

Calls within the local area can be free and chargeable. Configure which dialing rules must be used.

- All calls in the local area are free.
Phone numbers with the same area code as your own location are always dialed with the *local call* dialing rule.
- There are calls within the local area which are chargeable.
If there are chargeable phone numbers with your own area code, select the dialing rule *local call (chargeable)*.
 - Configure chargeable phone numbers
Configure the Prefix rule for which phone numbers with the dialing rule *Local call (costs involved)* have to be selected. All other phone numbers in the local area are dialed with the dialing rule *Local call*.
 - Configure free phone numbers
Configure the Area code rule for which phone numbers with the dialing rule *Local call* have to be selected. All other phone numbers in the local area are dialed with the dialing rule *Local call (costs involved)*.

Other area codes

Calls to other area codes may be free. Configure which dialing rules must be used.

- All calls to other area codes are long-distance calls.
Phone numbers with a different area code are always dialed with the *long-distance call* dialing rule.
- There are calls to other area codes which are free.
Switch on this option, if there are cost free phone numbers with a different area code and which have to be dialed with the rule *local call other area code*. Configure for every area code area code rule for which phone numbers with the rule *local call other area code* have to be selected.

Automatic configuration

You can access these rules automatically on the internet. For this purpose, the supplier <http://www.localcallingguide.com> is used. Please always check the accuracy of the imported data, no guarantee is accepted for completeness. If this service is not available, you need to configure the rules yourself.

Information as to which phone numbers must be dialed as local calls from your location is available from your phone company.

6.2.8 Dialing prefix rules

These settings are only required for countries in North America.

A dialing code rule defines a series of phone numbers which must be dialed with a certain dialing rule.

A phone number consists of an area code and a (subscriber) phone number. The first digits of the phone number are known here as a prefix.

Area code

Enter the area code which is to apply for this rule.

List of prefixes

Here you can enter a list of prefixes. If one of these prefixes matches the number to be dialed this rule applies.

Example

A phone number which fulfils this rule reads: +1 (202) 333-5678

Enter 202 as the area code

Enter 333 as the prefix

6.2.9 Location concepts

Configuration options for systems with several locations are displayed in the locations designs. If the telephone system to be set up involves a single location, it should be configured based on the Location Settings. An attempt should be made to include the following issues in the system design:

- **Consistent Phone Number Range:**
 - Internal phone numbers corresponding to DDI
 - Internal phone numbers that have not been assigned multiple times
 - Location phone numbers can be assigned in blocks
 - Extensions can be quickly dialed across locations (in connection with or without a cross-network identifier)

- Configure the individual locations based on the key performance indicators for the respective location.

- In Advanced Location Settings, enable *Enable Location Integration* and *Determine Phone Numbers from Other Locations*.

- To the extent that direct dialing of an abbreviated phone number across locations is possible, also enable *Abbreviate Phone Numbers before Dialing*. If dialing through cross-network identifiers is available, corresponding rules should be configured under PC Dialing. Alternatively, the telephone system can take over the conversion of the phone numbers to be dialed.

- **Arbitrary Phone Number Range:**
 - Internal phone number does not correspond to DDI
 - Internal phone numbers can be assigned multiple times
 - Location phone numbers cannot be grouped into blocks

The internal phone numbers must be converted to fully canonical external phone numbers for arbitrary phone numbers ranges and for phone numbers outside phone number range (DDI/internal). For this, enter the transformations in Internal Rules. In this manner, the fully canonical representation can be sought from the internal phone numbers in the associated databases and, vice versa, the fully canonical phone numbers can be abbreviated before dialing the internal extension numbers. The rules necessary for this should be entered under PC Dialing.

6.2.9.1 Dialing rules

The dialing rules influence the formatting of phone numbers when dialing from a PC.

The phone number is formatted in this order:

1. **Formatting**
All characters apart from + * # 0 1 2 3 4 5 6 7 8 9 a b c d e f g h i j k l m n o p q r s t u v w x y z are removed. All letters are turned into capitals.

2. **Vanity phone number recognition**
If the number contains one of the configured vanity numbers and if the letters following it are valid according to the ITU E.161 rules the number is first converted into dialable digits.
3. **Further formatting**
All digits apart from + * # 0 1 2 3 4 5 6 7 8 9 are removed.
4. **Recognition of specific numbers**
A decision is made based on specialnumbers.xml as to whether it is a special number (normally emergency numbers). If the number is stored in the xml file it is dialed externally without further formatting.
5. **Recognition of specific external numbers**
The decision will be made based on the rules for External Phone Numbers about whether an external phone number is involved or not. If an external phone number is detected, it will be dialed externally without additional formatting.
6. **Recognition of internal numbers**
A decision is made by means of the internal numbers as to whether it is an internal number in the system. If an internal number is recognized it is dialed without further formatting.
7. **Phone number standardisation**
The phone number will be converted to the international numbering plan.
8. **Transfer of Project Settings**
If dialing has been initiated in connection with a Project Identifier to be dialed through the telephone system, it will now be applied to the phone number to be dialed.
9. **Transformation of external phone numbers into internal numbers**
If you have configured a system phone number (system line) a check is made as to whether the phone number is an internal number. If an internal number is recognized the number is shortened.
10. **Using the PC dialing rules**
The phone number runs through the special rules for PC dialing.
11. **Abbreviation of long Phone Numbers from Other Locations**
To the extent that the Location Networking has been configured so internationally formatted phone numbers from other locations will be abbreviated to their DDI phone numbers, the phone number will now be abbreviated accordingly
12. **Transformation into a dialable number**
The phone number is reformatted according to the rules of the configured country in a dialable phone number. The dialing rules of countries are saved in the Configuration file *countries.xml*.
13. **Using external dialing codes**
The appropriate external dialing code(s) is/are added if the number has not been identified as internal yet.
14. **Using the PC final dialing rules**
The PC final dialing rules are applied directly before the phone number is sent to the phone system.
15. **Dialing the number**
The number is sent to the phone system.



Dialing Phone Numbers directly without using Dialing Rules
Prefixing the phone number with an exclamation point ! will avoid the use of dialing rules. The phone number will then only be transferred directly to the telephone system driver without any formatting.

4

6.2.9.2 Phone number formatting

A phone number which is sent from the phone system to the PC has to be formatted accordingly before further processing. The ProCall Attendant Console always uses Super-canonical phone numbers.

The phone number is formatted in this order:

1. **Formatting**
All digits apart from + * # 0 1 2 3 4 5 6 7 8 9 are removed.

2. **Application of the formatting rules**
The rules of the Formatting rules are applied. For further processing, the modified (if necessary) phone number is used.
3. **Removal of the external dialing code**
External dialing codes are removed if present. If an external dialing code is found the phone number is treated as an external number.
4. **Recognition of internal numbers**
Provided that no dialing prefix was removed, it is decided by the length and rules for internal phone numbers whether it is an internal phone number.
 - Detection of Special External Phone Numbers, when the phone number is external
 - Phone numbers in the DDI Phone Number Range, when the phone number is internal
 - Detection of Special Internal Phone Numbers, when the phone number is internal (the phone number may have been modified)
 - Detection of Phone Numbers from Other Locations, when the phone number is internal (phone number will be given the appropriate long distance dialing codes).
 - If the length of the phone number corresponds to the specifications for an Internal Phone Number, when the phone number is internal
 - Phone number is external
5. **Removal of call-by-call dialing codes (only outgoing phone numbers)**
Existing CallbyCall prefixes are removed for outgoing phone calls. The used prefixes are saved in a Configuration file *providers.xml*.
6. **Standardization of the number**
The phone number is now converted in a super-canonical phone number.

6.2.9.3 External rules



External phone numbers:

If a telephone system is used, a difference must be made between internal and external phone numbers. Normally, internal phone numbers are recognized based on the extension range and the length of an internal phone number that has been configured for the telephone system. Deviating from this, it may be necessary to classify certain numbers that would normally be understood as internal phone numbers as external phone numbers.

The rules permit detection of phone numbers based on Regular Expressions or direct comparison. Each entry can be configured individually. If the Replace With column has been entered, the phone number will be replaced automatically. Subsequently, the phone numbers will not be formatted further, but should however be transferred in international format. The configured rules will be processed from top to bottom, until a match has been found.

Check:

The rules can be checked immediately. Enter the corresponding expression in the Phone Number field. If the phone number was detected and how it has been implemented can be seen in the output row. The rule used for recognizing and formatting will be highlighted.

	<p>Specific Examples for the Use of Special External Rules:</p> <ul style="list-style-type: none"> • Detection of external phone numbers that would normally be understood as internal phone numbers (emergency numbers that are within the internal phone number range, but have not been assigned an extension (110, 112 and 911).
	<p>If a comprehensive set of rules should be established, the list can be maintained outside the administrator's utility. Existing rules can be exported as XML or CSV files, adjusted correspondingly and then re-imported.</p>

6.2.10 Formatting rules

You can change and individually format phone numbers with special rules. This can be done using Search/Replace or Regular expressions. Besides the formatting rules, phone numbers can also be changed internally/externally via those rules. Depending on whether the phone number has been registered by the telephone system or sent for dialing to the telephone system, the sequence of processing the rules will be changed. Additional information about the sequence in which the rules will be applied are described in the sections Phone Number Formatting and Dialing Rules.

The rules permit detection of phone numbers based on Regular Expressions or direct comparison. Each entry can be configured individually. If the Replace With column has been entered, the phone number will be replaced automatically. The configured rules will be processed from top to bottom until the first match has been found.

Formatting Phone Numbers that have been registered by the Telephone System

Note the order of the Phone number formatting.

- **Incoming**
Phone numbers for incoming calls which are reported to the PC by the phone system are formatted with these rules.
These phone numbers come directly from the phone system as dialable digits. They consist exclusively of digits and also * and #.
The phone number may include an external dialing code and, optionally, be an international, national, local or internal phone number.
- **Outgoing**
Numbers for outgoing calls which are reported to the PC by the phone system are formatted with these rules.
These phone numbers come directly from the phone system as dialable digits. They consist exclusively of digits and also * and #.
The phone number may include an external dialing code and, optionally, be an international, national, local or internal phone number.

Formatting Phone Numbers before They are transferred to the Telephone System for Dialing:

The sequence in which phone numbers will be adjusted for Dialing has to be observed.

- **PC dialing**
Phone numbers for outgoing calls which are to be dialed.
These rules will be applied after the phone number has been transferred in International Format.
At networked locations, this list will show generated expressions, given a corresponding configuration in the Advanced Location Settings, in order to convert long phone numbers from other locations into DDI phone numbers.
- **PC dialing final**
Phone numbers for outgoing calls which are to be dialed.
These rules are applied directly before the phone number is sent to the phone system.
The phone has already been formatted for dialing (with the External Dialing Code).



Specific Examples for Formatting Phone Numbers:

- Removing cross-network identifiers for registered phone numbers.
- Setting the cross-network identifier when a call should not go through the external telecommunications provider but rather through the internal location network.
- Replacing phone numbers when they should not be visible for other users at the application layer level.

➔ If a comprehensive set of rules should be established, the list can be maintained outside the administrator's utility. Existing rules can be exported as XML or CSV files, adjusted correspondingly and then re-imported.

6.2.10.1 Internal rules

Internal phone numbers

If a telephone system is used, a difference must be made between internal and external phone numbers. Normally, internal phone numbers are recognized based on the extension range and the length of an internal phone number that has been configured for the Telephone system. Deviating from this, it may be necessary to classify certain numbers as internal.

The rules permit detection of phone numbers based on Regular Expressions or direct comparison. Each entry can be configured individually. If the Replace With column has been entered, the phone number will be replaced automatically. Subsequently, the phone numbers will not be formatted further, but should however be transferred in international format. The configured rules will be processed from top to bottom, until a match has been found.

Check:

The rules can be checked immediately. Enter the corresponding expression in the Phone Number field. If the phone number was detected and how it has been implemented can be seen in the output row. The rule used for recognizing and formatting will be highlighted.

- ➔ Specific Examples for the Use of Special Internal Rules:
- Detection of internal phone numbers not covered by the rules configured in the Telephone System.
 - Conversion of internal phone numbers to external, when internal phone numbers and extensions (DDI) are different.
 - Detection of internal phone numbers in system groupings with substitution through their representation in international format.

➔ If a comprehensive set of rules should be established, the list can be maintained outside the administrator's utility. Existing rules can be exported as XML or CSV files, adjusted correspondingly and then re-imported.

6.2.11 Vanity

Letters marked on the phone's keypad makes it possible to apply for numbers whose alphameric conversion corresponds to a certain name or concept. These are phone numbers which can be written as a text. Vanity phone numbers can be used in different areas (0700, 0800, 0180...). For example: 0800HANSMEIER.

Resolve vanity numbers:

Here you can define phone numbers for which you wish to use vanity numbers. Enter the dialing code without the national identifier number, e.g. 700, 800.

6.3 Regular expressions

Regular expressions are patterns with which strings can be searched. It is thus possible to determine whether the string fulfils specific parameters (length, begins with certain numbers, etc.) or to replace certain parts of the string.

Search for

This expression is used on the string. If a match is found, the string is replaced with the *replace with* expression. Hint: The caret (^) key can be found at the upper left of a keyboard with German layout.

A brief overview of the permitted expressions:

Character	Description
^	The beginning of the digit chain. The expression "^o" finds "o" only at the beginning of the phone number.
^	The caret directly after the left bracket ([]) has another meaning. It is used to exclude the other characters within the bracket. The term "[^0-8]" permits digits from 0 to 8 only.
\$	The dollar character labels the end of the character string. The term "152\$" is valid for phone numbers which end with "152" only.
	The slash allows both digits each side of it. The expression "8 9" allows "8 or "9".
.	The dot (.) permits any character (or any digit).
*	The asterisk (*) shows that the characters to its left must be present 0 times or more.
+	The plus sign (+) is similar to the star except that the character to its left must be present at least once.
?	The question mark (?) shows that the character to its left must be present 0 or 1 times.
()	The round bracket marks the expressions which are available in the replace with field.
[]	The square bracket marks a number of characters which are permitted at this location.

Replace with

Insofar as a match with the string was found, the string is replaced by the expression entered here. Parts of the found string can be inserted here:

\1 reads out the first expression marked with '()' in the *search for* field.

\2 reads out the second, etc..

Examples:

Effect	Search for	Replace with
--------	------------	--------------

Removal of a leading 0	$^0(.*)$	$\backslash 1$
Replacing a 80 at the beginning of a number (e.g. targeted external dialing code) with 0	$^80(.*)$	$0\backslash 1$
Removal of a private PIN which is added to the beginning of a phone number as 50xxx	$^50[0-9][0-9][0-9](.*)$	$\backslash 1$
Suppression of all numbers which are signalled internally (3 digits)	$^[0-9][0-9][0-9]\$$	
Add an external dialing code code (leading 0) for all numbers with more than 3 digits	$^([0-9][0-9][0-9].+)$	$0\backslash 1$
Add the phone system base number (03012345) to all internal numbers (1 to 3 digits in length)	$^([0-9][0-9]?[0-9]?)\$$	$03012345\backslash 1$
Add your own area code to all numbers which do not start with 0 and are at least 4 digits long (and thus not internal numbers).	$^([\^0][0-9][0-9][0-9].*)$	$08151\backslash 1$

6.3.1 Advanced

Display all messages

estos ProCall Attendant Console often uses message windows which you can automatically suppress for future similar cases with the "Do not show again" option. Use this function to re-display all message windows which would otherwise not be opened again.

Reset layout

Click here to reset the current layout of the client to default. This implies restoring the default column widths in the tabs (e.g. journal, planned calls etc.) and a reordering of all tabs in the main window. Contacts saved are still remain.

6.3.2 Dialog adaptation with Templates

estos ProCall Attendant Console uses XSLT templates to display XML data as HTML pages. The XSLT templates are in the *Templates* or *Templates/default* folder.

Directory	Deployment
<i>templates</i>	You should save files you have changed in this directory if you wish to change one of the files supplied in templates/default
<i>templates/default</i>	Configuration files which were installed with the product. These are overwritten if the product is updated.

XSLT processor


estos ProCall Attendant Console provides the files in XML format. These XML files are processed into an

HTML page with the help of an XSLT template and an XSLT processor. Sablotron or Microsoft® XML Parser are used as XSLT processors.

Development of own templates


You can develop and use your own templates. You should familiarise yourself with XSLT syntax for this. You can find help on the subject at <http://www.w3schools.com/xsl/> or the Microsoft® MSDN pages.

If you wish to use templates you have developed by yourself these should be stored in the *template* directory. Your changes will then not be lost if an product update is installed.

Template	Deployment
<i>common.xslt</i>	Provides different template functions for e-mail and web links and for transcoding sets of characters
<i>unanswered.xslt</i>	E-mail messages regarding unanswered calls. More precise details can be found in the estos UCServer help file.
<i>contact.xslt</i>	Overview page in the Contact details window.
<i>RemoteContact.xslt</i>	Is used in the Call window to prepare the details for the current dialog partner. The template defines which contact details are displayed.
<i>HoldContact.xslt</i>	Is used in the Call window to prepare the details for a dialog partner on hold. The held dialog partner is displayed if a further estos ProCall Attendant Console user is holding a participant and calls you. The template defines which contact details are displayed.
<i>LocalContact.xslt</i>	Is used in the Call window to prepare the details for a called contact. The called contact is displayed if a contact for an incoming call to the phone number is found. You must activate the hotline service in the settings for Incoming calls for this. The template defines which contact details are displayed.
<i>RedirectedContact.xslt</i>	Is used in the Call window to prepare the contact details for a redirected call. You are shown the contact for whom the call was last signalled. The template defines which contact details are displayed.
	When changing the templates, please keep in mind that the <i>common.xslt</i> must always be in the same directory as the template using the <i>common.xslt</i> .

6.3.3 Function control via Windows® Registry

All necessary settings which are saved in the Windows® registry can be changed in the estos ProCall Attendant Console user interface. You can, nevertheless, also activate or deactivate special functions in estos ProCall Attendant Console by means of certain keys.

	Please note that the functions mentioned here only make sense in exceptional cases and their use is
-------------------------------------------------------------------------------------	-----------------------------------------------------------------------------------------------------

not generally recommended.

All the following listed registry values are expected in the **HKEY_CURRENT_USER\Software\estos\UCServer4\CtiMain** key. The registry value must be created below this key to enable the relevant function in estos ProCall Attendant Console.

Registry entry	Type	Meaning
JournalAutoCreateFlags	DWORD	<p>With this registry entry you can control whether estos ProCall Attendant Console generally automatically creates a journal entry in Outlook® for all incoming and/or outgoing calls.</p> <p>Set the DWORD value to "1" to always automatically create an Outlook® journal entry for all incoming calls. With value "2", all outgoing calls are always included. Set the value to "3" to log all calls in Outlook®.</p>
EnableOutlook® EnableMAPI	DWORD	<p>Use these two registry values if estos ProCall Attendant Console is to use neither Outlook® nor MAPI.</p> <p>To switch off the connection to Outlook® or to not use MAPI, set both DWORD values to "0".</p> <p>These registry entries have no effect if you do not have Outlook® installed or if no MAPI is available in the system. Please also note that these values have no effect on the Outlook® plug-in.</p>
EnableLotusNotes	DWORD	<p>Use this registry value if estos ProCall Attendant Console should not use IBM Notes® which is installed on the computer.</p> <p>Set the DWORD value to "0" to switch off the connection to IBM Notes®.</p> <p>This registry entry has no effect if you do not have IBM Notes® installed.</p>
EnableEWS EnableEWS	DWORD	<p>Use this registry value to allow estos ProCall Attendant Console to use Exchange Web Services.</p> <p>To enable Exchange Web Services, set this DWORD to "1".</p>
EnableGoogle EnableGoogle	DWORD	<p>Use this registry value to allow estos ProCall Attendant Console to integrate Google (requires configuration by your system administrator).</p> <p>To enable Google, set this DWORD to "1".</p>

<p>EnableWindowsStore EnableWindowsStore</p>	<p>DWORD</p>	<p>Use this registry value to allow estos ProCall Attendant Console to integrate Windows® 10 Apps (Calendar, People, Mail).</p> <p>To enable this integration, set this DWORD to "1". This value has no effect on older versions of Windows®.</p>
--------------------------------------------------	--------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

6.4 Telephony

In **Telephony** you can customize the call window to your needs, choose settings for incoming, outgoing, unprocessed and planned calls and also define projects. Additionally you can configure your Bluetooth connection here.

- Conversation window
- Incoming calls
- Outgoing calls
- Planned calls
- Projects
- Bluetooth Cell Phones
- Call Protection

6.4.1 Conversation window

Display automatically for incoming calls

Display automatically for outgoing calls

You can define whether you wish the call window to be displayed for incoming or outgoing calls. If the window is not displayed automatically you can display it at any time during the call via the estos ProCall Attendant Console task bar.

Always display active calls as the topmost window

You should activate this option if you wish to always display active calls as the topmost window. If the window is automatically displayed, it is normally displayed as the topmost window for an incoming or outgoing call but can then subsequently be covered by other windows. You can bring all current calls into the foreground via the tray icon at any time.

Duration of displaying the conversation window after the call ends

After ending the telephone call the call window remains open for a certain amount of time. During this time it's possible to allocate this call, for example to a certain Project or to enter a short note. Here you can specify how long the window should remain open.

Transparency, support display and fading out

The call window supports transparency and is normally faded in and out. If you do not wish to use this function you should deactivate the transparency.

Window position

You can define the position as to where the call window opened by estos ProCall Attendant Console. Call windows for prepared calls are excluded. These windows are always opened at the current position of the mouse.

- **Default position (task bar icon)**
ProCall Attendant Console opens the conversation window at an appropriate location on the screen. Other, already open windows of ProCall Attendant Console are not overlaid.

- **Remember last position**
The conversation window appears again at the same position where you have closed it the last time or where it was automatically hidden.
- **Define position using preview**
Open a call window with the preview button and place it where windows should open it in future. Moving the conversation window during a call has no effect on the display position.

6.4.2 Incoming calls

Support for Hotline-Services (client function)

The hotline service analyses the number called for incoming calls (multi-entity capability). Analysis of the number called can be used to differentiate between various companies if you have to announce yourself differently depending on the number called (e.g. for a secretarial service).

Activate the option **Display called contact**, so that the contact information is displayed in the Call window of an incoming phone call. What information should be displayed can be defined via a template.

Unanswered calls

The estos UCServer recognizes missed phone calls and checks whether the phone call was answered from a call group or call diversion. Notifications can be sent as an e-mail for these missed calls. With these settings it can be defined to which e-mail addresses unanswered phone calls are sent and whether these notifications should be also sent if the user is logged on to the server. Moreover, unanswered calls can be automatically marked as processed when a telephone call was made to the same contact at a later date.

➔	In addition to the server-side search for client contacts, local client folders can be specified in the settings of the Data sources.
➔	If the matching client contact should be opened automatically during the phone call, then it can be specified in the settings Actions.

6.4.3 Outgoing calls

Call preparation

The option **Always prepare phone calls** enables you to set projects projects or set the private marker on the calls. This setting is not needed if projects or the marking of private calls are not used.

Automatic redialing

If an outgoing call does not go through because the line is busy, you can start automatic redialing in the call window. You can define how often the system will try to connect the call and at which intervals. Automatic redialing is terminated as soon as the line is no longer busy or the set number of attempted calls has been reached.

Caller ID suppression

You can activate the suppression of caller ID for outgoing calls if this is supported by your telephone system. You may activate caller ID suppression for all outgoing calls or choose case by case whether you wish to suppress caller ID. If you wish to suppress caller ID in individual cases only, an additional button for activating or deactivating this option appears in the call window. Please keep in mind that this option must be activated before you start the call so that the caller ID can be suppressed.

6.4.4 Planned calls

With planned calls, you can have yourself reminded at a specified time of calls to be made or plan upcoming calls in advance. Planned calls appear in the main window on the tab of the same name.

estos ProCall Attendant Console offers you two options for managing planned calls:

estos ProCall Attendant Console

- **Administration with estos UCServer (recommended):**
Planned calls are only saved in estos UCServer and can be added and changed in the estos UCServer editor.
- **Management with Outlook®**
Planned calls are saved exclusively in Outlook® and can only be saved with the Outlook® editor. Please note that the possibilities for subsequent alterations to the phone number and the linked contact are limited as only Outlook® contacts can be subsequently linked.

6.4.5 Projects

estos ProCall Attendant Console helps the user assign calls to previously defined projects. This feature is also available from the Journal as well as the telephone system itself. The project identifier should be selected from the server through the system as would be appropriate for the project settings. Making private calls through so-called calling card providers is the exception to this. If a call is marked as private, the call through the telephone system can be configured using the identifying numbers.

If the **Mark private calls** option is activated a call can be marked, for example, as private in the call window.



To prevent others seeing private numbers or callers they can be marked as private. Any call information is not visible to others in the journal.

Prerequisite: estos UCServer is set to not save phone numbers. See also Telephone Journal in the estos UCServer help file.



If private conversations are not allowed in the company, having the administrator deactivate this option in estos UCServer or in the group policies is reasonable.

Use projects and code numbers









In estos ProCall Attendant Console, projects are predominantly configured for the journal. In addition, specific PINs and calling card providers can be defined for private conversations. If the project has been defined as a private call then the PIN will be used for the call and it will not be logged in the journal.

The following rules apply:

Character	Deployment
0-9 * #	Digits which are dialed normally
C	Here you wait for the remote station to accept the call.
e, E	Place-holder for entering a PIN. With E, the number of digits for entry is not important. With e, the number of digits is defined by the number of letters (eee for three digits).
u, U	Space for the input of a user ID. With 'U' the number of digits input is not important. With 'u' the number of digits is defined over the number of the letters ('uuu' for three digits).

p, P	Dialing pause: 'p' for 0.5 seconds, 'P' for 1 second.
N	Space for the number to be chosen. If the space is not set, the number is automatically transferred to the end.
J	Defines, if available, that the user login and pin number entered by the user is noted in the journal.
X	If available, the phone number should be dialed with an external prefix. If 'X' is absent the phone number is dialed in national format (03012345678).

In the user interface configured projects are visualised centrally and locally with differently coloured Icons:

 Projects configured in estos UCServer.
 Project for the journal
 Project for dialing
 Project for dialing and for the journal
 Project configured in estos UCServer which is processed as a private call
 Projects configured in estos ProCall Attendant Console:
 Project for the journal
 Project configured in P estos ProCall Attendant Console which is processed as a private call

6.4.6 Bluetooth

Support for Bluetooth Cell Phones

Cell phones can be connected with the PC using Bluetooth. This connection will make controlling and monitoring of the telephone possible. Furthermore an audio device connected to the PC (e.g. headset) can be used for conversations by cell phone. The telephone must support the Bluetooth Hands-Free Profile. This is also be used with a speaker phone in the car.

Connect New Devices with the PC (Bluetooth pairing)

The cell phone must be connected with the PC (Bluetooth pairing) in order to be able to use it. During pairing, Bluetooth must be active and visible at the cell phone while new phone devices in the Bluetooth configuration of the Windows® Control Panel are being searched. If pairing is successfully completed the new phone device appears listed available in the Bluetooth configuration of estos ProCall Attendant Console.

All cell phones that have been connected with the PC can be automatically used. Alternatively, only those telephones that are desired for use can be selected from the list of connected devices. If the cell phone is successfully connected with estos ProCall Attendant Console you see at the Presence area of the Main window a green line symbol. If no Bluetooth connection exists the line symbol turns to be grey. If you have more than

one line available and you wish to do an outbound call you have to select the related line symbol of the cell phone to be used. Then enter the phone number of the destination party at the search line or select an ActiveContact in the Favorites area and press the symbol for calling.

Phonebook

The Phonebook of the mobile phone/cell phone can be optionally integrated.

Offline journal

If the Bluetooth connection will be interrupted and becomes available at a later moment, calls that have been made in the meantime are synchronized with the journal based on the imported call list.

Please note that no call duration can be determined from the imported entries for the journal.

iPhone® mobile phone via Bluetooth

The transferred content of the imported call log has been changed by the last iOS versions.

The imported call log contains only the most recently calls per subscriber, each for incoming, outgoing or missed calls.

Call Protection

The settings for Call Protection are also valid for cell phones connected via Bluetooth with the estos ProCall Attendant Console client.

Enable PC audio devices

If you like to use the PC audio devices for speech conversations via cell phone, the setting "Enable PC audio devices" must be checked (default setting).

Deactivate hands-free system driver

Because of technical restrictions only one hands-free driver can be active at the same time. estos ProCall Attendant Console can automatically disable the system driver to enable this functionality.

Configuration of the PC audio devices

The PC audio device can be configured with the Audio/Video Wizard. The Wizard is started automatically during the initial setup procedure. But the Wizard can be started anytime by pressing the Audio/Video symbol at the Presence area of the main window. If you have enabled the checkbox "Enable Hook switch support" ("HID" buttons) in the Wizard, calls via cell phone can be accepted or dropped per PC audio device buttons.



Conversations via cell phone, via Audio/VideoChat and via Softphone can be done using the same PC audio device (e.g. headset).

Conversations per Bluetooth and PC audio devices

An active call is being represented by the Call window. In the conversation window near the call control buttons a small menu allows using further features like sending DTMF tones or moving audio from the PC towards the cell phone or back.

If you have paired your cell phone with estos ProCall Attendant Console and you establish a call by using your cell phone (e.g. accept or dial a call), audio is active on your cell phone. But if you establish a call by using the PC, the PC audio devices are being used. This is because if you are with your cell phone in the Bluetooth signal range of the PC but not at your desk, audio should be automatically active at your cell phone.

Technical information

You may pair several cell phones with estos ProCall Attendant Console at once. Please be aware that one active audio stream via Bluetooth is supported with one of the paired cell phones. Thus if another paired cell phone does calls while the PC audio devices are already in use, you talk on the related cell phone.

PC audio devices are supported using sampling rates between 8 kHz and 96 kHz (8, 16, 22.05, 32, 44.1, 48, 96 kHz). It is recommended to use a headset.

6.4.7 Call Protection

6.4.7.1 Link Call Protection to "Do Not Disturb" presence status

You can link "Call Protection" settings to the "Do Not Disturb" presence status. This requires that the telephone system supports that function for your telephone, or this function must be enabled in UCServer for the Softphone line.

"Do Not Disturb" presence status controls Call Protection

Setting a "Do Not Disturb" presence status activates "Call Protection" for all telephone and softphone lines and also for AudioChat and VideoChat (incl. screen transfer).

Call Protection controls "Do Not Disturb" presence status

Activating "Call Protection" for a line causes your presence status to be automatically set to "Do Not Disturb". "Call Protection" on other lines is not affected by this, nor by the option "'Do Not Disturb' Presence Status Controls Call Protection'.

Apply Call Protection to all communication devices

If you change Call Protection (DND) on your desk telephone, this setting is applied to all telephone and softphone lines and also to AudioChat and VideoChat. If 'Call Protection Controls "Do Not Disturb" Presence Status' is activated as well, presence status is set accordingly.

6.4.7.2 Reject calls when busy

If the telephone system is configured so you can receive a second call (call waiting), a second call that comes into your telephone or softphone is signaled to you during a telephone conversation. In addition, the various communication devices in ProCall (telephone, softphone, audio chat, video chat) work independently of one another. Second calls may therefore occur on just one communication device, or on a set of communication devices. The following settings allow you to control this behavior.

Busy on Busy

If this option is activated, second calls made to the line on which you're making a call are declined with "Busy".

Busy on Busy across multiple devices

If this option is activated, new calls that come in on other lines during a telephone call are declined with "Busy".



If unconditional call forwarding (forward all calls (both internal and external)) is set for a line, Busy on Busy will not be activated for that line.

6.5 Search

In **Search** you can control the search behavior of estos ProCall Attendant Console, in particular by selecting which data sources and search-parameters should be used in the detail search.

- Data sources
- Search parameter
- Search result

6.5.1 Data sources

The data source settings contain the list of all contact data sources which are to be used when searching for contact definition. estos ProCall Attendant Console automatically inserts the data sources for estos ProCall




Attendant Console users, the lines, the estos ProCall Attendant Console favorites and the estos MetaDirectory centrally configured in estos UCServer. Also data sources which are administratively defaulted by group guidelines are automatically entered.

Using the data source estos ProCall Attendant Console favorites you can search all contacts in your favorites and thus find quickly.

In addition, your personal inbox is imported from Outlook® when estos ProCall Attendant Console is started if you have Outlook® installed on your computer and have not specified any other folders.

6.5.1.1 General settings

The search behavior can be set for each data source in the list. The general settings can be changed directly in the overview list or by clicking the **Edit** button on the **General** tab.


-  **Use in search filter "All"**
If this option is selected for a data source the data source is searched if the "All" filter is selected in the search field.
-  **Search on incoming call**
For every call, estos ProCall Attendant Console automatically searches data sources for the phone number in order to find the call partner. You can define here which data sources are to be used for this. It is recommended that especially slow data sources are not searched when contact search.
- **Use if tenant function**
In addition to the phone number search to find out the call participant, ProCall Attendant Console can also search a contact, the client, for the phone number on your own telephone. This function is useful, e.g. for hotline services, and you should only activate it if the data source contains client contacts and you want to show the client contact, e.g., in the call window. Please note that the tenant function can not be used for the data source "estos ProCall Attendant Console user" as well as for phonebook data sources.
-  **Treat as unpersonalized data source**
As well as your personal contact data sources you can also use estos ProCall Attendant Console with unpersonalized data sources (mainly phone books). However, the search of phone books only makes sense if there is no contact in your personal contact data sources which corresponds to the search criteria. Activate this setting if the data source should only be searched when no contact is found in the personal data sources already searched. Phone book data sources are a typical application case.




6.5.1.2 Data source search sequence:

estos ProCall Attendant Console permits you to define the order in which the data sources are searched. The topmost data source in the list is always processed first. Click the **Move up** button to move the selected data source up one place. Similarly, use the **Move down** button to move the selected data source one place lower down in the list. Please note that all data sources with the **Treat as phone book** option are always searched at the end and therefore must always be at the bottom of the list.

6.5.1.3 Adding data sources


New data sources can be linked at any time in estos ProCall Attendant Console. For this, click the **Add** button and select the data source option.

-  **Outlook®**
Click here to add an Outlook® mailbox or a specific Outlook® contact folder to the search list. Please note that you can only select mailboxes or contact folders in the selection dialog. If you add a mailbox this is automatically configured so that all subordinate contact folders are also used in the search. Subordinate folders are not, however, included for added contact folders. This behavior can be altered at any time with **Edit**.



-  **Exchange Web Services**
The Contacts folder can be added using Exchange Web Services from here. As with Outlook®, all sub-folders for mailboxes will be used automatically, but not with normal folders.
-  **IBM Notes®**
Click here to add a IBM Notes® address book to the search list. The configuration dialog assists you with integration and offers default settings. You can change the configuration at any time with "Edit".
-  **ODBC**
Click here to add an ODBC data source to the search list. You can thus use contact data which you have stored, for example in a Microsoft® Excel file or a Microsoft Access® database, directly in estos ProCall Attendant Console.

The configuration dialog supports you with connection and specifies default values. You can modify the configuration at any time with **Edit**.

Please note that for this function the appropriate ODBC driver must be present on your system. The use of a estos MetaDirectory is recommended to integrate larger data stocks for performance reasons.



-  **Add phone book**
estos ProCall Attendant Console offers you the option of adding phone books installed locally on your computer. Although estos ProCall Attendant Console automatically recognises locally installed phone books it may be necessary to specify the installation manually. When installing "Das Telefonbuch Deutschland" please indicate the installation path of the product in a manual configuration, when installing "TwixTel" the path to the Data-CD must always be specified.

You can also integrate phone books into estos ProCall Attendant Console which are not installed locally but centrally. For this, you must configure the phone book in the estos MetaDirectory and connect the estos MetaDirectory as a phone book.

-  **Add MetaDirectory or LDAP data source**
You can integrate both a estos MetaDirectory and normal LDAP data sources into estos ProCall Attendant Console with the help of the database wizard. Field allocation is automatic in the case of estos MetaDirectory.
-  **DATEV SDD**
Click here to add the DATEV SDD database to the search list.

6.5.1.4 Editing data sources







Specific data source properties can be viewed or modified via the **Edit** button. Alternatively you can double-click a data source list entry.

-  **Adjust favorite data source**
In the event that a company name has not been explicitly provided by the federation participant, check the **Fill empty company names from the presence domain entries for federation contacts** checkbox, to find Federation contacts based on company name when searching Favorites. When checked, the presence domain will be interpreted as the company name for federation contacts.
-  **Edit Outlook® folders**
Select the **Include all sub-folders when searching** option on the **Advanced** tab if all subordinate contact folders should be searched in addition to the folder itself.

On the **Name search** tab you can specify a list of fields which should be additionally included in name searches in Outlook® folders. The Last name, First name and Company fields are already searched by default. Please note that the name search fields apply globally for all Outlook® folders.

Example:






Click **<Add field here>** and select the **Item.Department** entry from the list. The subsequent name search will then find all Outlook® contacts which match the search criterion in the **Department** field.

-  **Edit Exchange Web Services**
The settings available are the same as those for Outlook® folders.
-  **Edit IBM Notes® folders**
The tab **Advanced** displays the most important details of the selected IBM Notes® Directory. Select the button **Configure** in order to change the parameters.
-  **Edit ODBC connection**
The tab **Advanced** displays the most important details of the selected ODBC connection. Select the button **Configure** in order to change the parameters.
-  **Edit phone book**
Here you can query the installation path and the current status and, if necessary, information about the connected phone book. Please note that the installation path can only be changed if you remove and re-attach the current phone book.
-  **Edit MetaDirectory or LDAP data source**
On the **Advanced** tab, information can be retrieved about the selected data source or configuration of the data source. The database wizard assists with this. Please note that a centrally configured estos MetaDirectory can only be changed in estos UCServer and not in estos ProCall Attendant Console.
-  **Edit DATEV SDD data source**
Check **Use Comments from Communication Details as the Contact Person's Name** so that contacts maintained in the Comments entry in DATEV Arbeitsplatz Pro can also be found.

Please note that with data sources that are administratively defaulted by group guidelines, the configuration cannot be edited by the User.

6.5.1.5 Deleting data sources

Click the **Delete** button to remove a data source. Please note that some data sources cannot be removed. These include the estos ProCall Attendant Console users, estos UCServer's lines, the estos ProCall Attendant Console favorites and the estos MetaDirectory centrally configured on estos UCServer. Also data sources cannot be deleted which are administratively defaulted by group guidelines.

	If a data source could not be integrated this is indicated by an exclamation mark in the data source icon. An error description is displayed in the tooltip if you place a mouse pointer over the data source icon.
	Local mail boxes from Outlook® or IBM Notes® are added automatically at the start of estos ProCall Attendant Console if no data sources were configured for Outlook® or IBM Notes®.
	If at Start, estos ProCall Attendant Console recognises a phone book that until now is not configured, this is included in the data source list automatically.
	"Das Telefonbuch Deutschland" must be installed on your computer with the phone book data bank. To copy the phone book database (without installation) is not sufficient.
	The integration of DATEV automatically prioritizes contacts from DATEV data sources during phone number resolution after initial installation. This can be changed by the user in the data source settings. If the DATEV workstation is started, a search hit from the DATEV data source is always preselected in the client, regardless of the prioritization of the data sources.

6.5.2 Search parameter

On the settings page "Search parameters" you can define the fields which estos ProCall Attendant Console uses in the detail search. There you can define their order and other options for the detailed search.

The following search parameters are preset in estos ProCall Attendant Console:

- Last name
- First name
- Company
- Customer ID
- Department
- Postcode/City
- Street
- Phone number
- Presence-/e-mail address

Customize the search parameter sequence

Use the "Up" or "Down" buttons to shift the search-parameter either upwards or downwards in the list. The search-parameter order in the list determines their position in the detail search.

Activate or deactivate search parameter

The search parameters can be activated and deactivated. Only enabled search parameters are used in the detailed search. Checkmark the box on the list to activate the search parameter. Delete the checkmark on the list entry not to use the search parameter in the detailed search.

User-defined search parameter

User-defined search parameters can also be laid out in estos ProCall Attendant Console beside the given search parameters. These allow the user to consider other contact fields not normally displayed in the detail search.

Configure user-defined search parameter

Click on **Add** to create a new user-defined search parameter. Click on **Edit...** to change the selected user-defined search parameter.

1. Allocate a name to the user-defined search-parameter. This name is used in the list of all search-parameters and in the tool tip for the detail search.
2. Select the corresponding contact fields which should be considered in this search-parameter. A user-defined search-parameter can also search several contact fields at the same time. In this case the contact is found when the search word matches the content of only one contact field.

Example:

A user-defined search-parameter should be added in order to find a contact by its SIP-Address in the detail search.

1. Enter **SIPAddress** in the name field.
2. Tick the box before the field name to select the "SIPAddress" in the contact field list.
3. Confirm your entry with **OK**.



With the command **delete** every user-defined search-parameter can be deleted again. Please note that only user-defined search-parameters can be edited or deleted.

6.5.3 Search result

Here the search result can be adapted and defined for the user. With this the order of the contact fields to be displayed can be set as well as their appearance and click actions.

Available contact fields

In the list of the available contact fields the corresponding tick-box next to a contact field can be activated if this contact field should always be shown in the search results. With the buttons **Up** or **Down** you are able to change the order of the contact fields in the search results.

Customize Layout settings

On the **layout** tab the general appearance of the selected contact field can be adapted.

Layout Option	Description
Display in compact view	Indicates whether the contact field is also displayed in the compact view. If the box is not ticked, the contact field is only shown in the detail view.
Display field names	Specifies if the field name should be displayed next to the account of the contact field.
Insert paragraph before field	Allows a better overview with the help of paragraphs to group and structure contact fields.
Display in bold type	With this option the contact field is displayed in bold type and is thereby emphasised.




tab **Customize field**

Here you can further customize the appearance of the contact field selected from the contact field list. The setting possibilities vary, depending on the selected contact field.

Specify contact field actions

On the **Actions** tab, actions which are executed by clicking on the contact field can be changed. All contact functions of the contact menu are available here as well as all User-defined actions.

In addition, up to three different actions can be put on one contact field, either by using no key, holding down the CTRL key or holding down the Shift and CTRL key together, while clicking on the corresponding contact field in the search result list.

	The button Default resets the default layout.
	Only contact fields which are not empty are displayed in the search result.
	All contact fields are displayed in the search result (including the compact view) which were searched for.

6.6 Integration

Calendar and journal connections are controlled in **Integration**.

- Calendar
- Journal
- DATEV

6.6.1 Calendar

Appointment dates are transferred from the client to estos UCServer in order to permit estos ProCall Attendant Console to display them and pass them on. They are stored temporarily, consulted for creating your own presence and displayed to other users who have the appropriate user rights.

Appointment details can presently be read either from the Outlook® or from the IBM Notes® diary. In Windows® 10 you can also use the included calendar app.

If your administrator has installed this, it is also possible to use Google Calendar.

If you use multiple Systems, you can select the system you use as the data source.

A user has the option of limiting the amount of appointment data which is made available to the system. The following options can be selected:

- **None**
No data is transferred to the server. This data is then not displayed to other users and the information is not included when determining your own presence status.
- **Public appointments only**
Only appointments which are marked as public are transferred to the server. They are then available for other users and for determining your presence.
- **Public appointments as well as the status and times of private appointments (default setting)**
All appointments are transmitted to the server, but for private appointments only the start and end time and the appointment status (busy, absent, etc.) are transmitted. This will show their presence in private appointments according to the appointment status for other users, without giving other users access to any other information (such as the subject).
- **Private and public appointments**
All appointment information is transferred to the server and is available to other users and can be used to determine your presence status.

6.6.2 Journal

estos ProCall Attendant Console uses a journal provided by the server. All conversations and calls will always be stored on estos UCServer irrespective of these settings. Specifically, estos ProCall Attendant Console enables you to copy journal entries also into Outlook® or IBM Notes®.

Select data source:

If you use both Outlook® and IBM Notes®, you may select your preferred system as a data source.

Setup journal file

estos ProCall Attendant Console always lays out the journal copies in the set journal folder. If another journal folder should be used, this can be changed here with the "Search" button. Please note that only the journal folder can be selected in the choice dialog. Select "default" to activate the default-journal folder.

Create automatic journal copies

In addition to the option of placing a copy of a journal entry in Outlook® or IBM Notes® manually via the context menu, estos ProCall Attendant Console can also prepare automated journal entries of telephone calls in Outlook® or IBM Notes®:

- **For a call memo**
Activate this option, and estos ProCall Attendant Console will always store a journal copy in Outlook® or IBM Notes® as soon as you enter a memo about the call in the call window while you speak.

- **Contact from own mailbox**
Activate this option and estos ProCall Attendant Console will always store a journal copy in Outlook® or IBM Notes® as soon as a contact from one of your personal contact files was assigned to the call.

★	Use the Journal browser for a more detailed call journal.
➔	Since estos ProCall Attendant Console keeps a journal provided by the server, journal entries for every call in Outlook® or IBM Notes® are not necessary. This saves unnecessary objects and ensures lasting high-quality performance of Outlook® and IBM Notes®, respectively.
➔	You can see an overview of your last calls in the estos ProCall Attendant Console main window if you click the Journal tab.
➔	For special requirements, it may be necessary to save all calls as journal entries in Outlook® or IBM Notes®. This service can be activated in the Windows® registry. Details can be found at Control functions via Windows® Registry. Please note that activation of this function is not recommended!

6.6.3 DATEV integration - Automatic Data Transfer

estos ProCall Attendant Console can automatically synchronize data between DATEV Arbeitsplatz Pro and estos ProCall Attendant Console in large part. By setting "Automatic Data Transfer", all phone calls will be synchronized (regardless of any properties) with DATEV Arbeitsplatz Pro. Setting the following options has a restrictive effect (similar to black listing) on synchronization with DATEV Arbeitsplatz Pro.

- **Answered Calls Only:** Missed calls will not be synchronized automatically with DATEV Arbeitsplatz Pro. However, they can be subsequently synchronized from the estos ProCall Attendant Console Journal for Unanswered Calls.
- **External Calls Only:** Calls from your organization will not be automatically synchronized against DATEV Arbeitsplatz pro.
- **DATEV Contacts Only:** Only those calls from contacts that have already been created in the DATEV master data service (SDD) will automatically be synchronized with DATEV Arbeitsplatz Pro. A connection to the DATEV master data services (SDD) must have been configured already and be available for this feature.

6.7 Services

- Mail dispatch
- SMS text dispatch

6.8 Notifications

The estos ProCall Attendant Console supports the sending of messages for unanswered calls

The contents of a message can be customized by means of a template. The contents of the email will be opened with the help of a XSL template as an html. See XSL Templates.

Recipient

- **no participant**
No e-mail notifications for missed phone calls are dispatched.

- **first participants, who have not answered the call**
The first participant whose phone has rung receives the notification about the missed phone call.
- **last participants, who have not answered the call**
The last participant whose phone has rung receives the notification about the missed phone call.
- **all participants, who have not answered the call**
All participants whose phone has rung receive a notification about the unanswered phone call.



The estos ProCall Attendant Console supports the detection of parallel connections, group calls, cyclical call distribution and forwarding in the call phase. This makes it possible to avoid duplication of delivery of unanswered calls, even if the call rang on several telephones.

Send e-mails from the client

If you do not have your own mail server, emails can be delivered by the client. However, we recommend having emails sent via the Email-Delivery des estos ProCall Attendant Console. You can also use an external mail server.

This enables the dispatch of missed phone calls as e-mails, for example, to a mobile phone even if the personal computer is not running.

Send e-mail as well if the call is answered by third party

If this option is enabled an Email is sent to the called party even if the call is accepted by another party (e.g. per pickup).

Use the caller's e-mail address as the sender

If this option is active, the e-mail notification has the caller as a sender. With this option you permit a direct contact with the caller.



If you use a Groupware solution for absence notifications, the caller receives a message with the absence note you provided. With this the caller is informed when the person can be contacted again or if specified in the absence note they can contact a colleague.

Attach caller contact details to the email as a vCard

Contact information determined through contact search can be automatically attached as vCard to an email. This allows access to all the caller's contact data, even when on the road.

Give Telephony link the following prefix

Enable this option, if a phone number should be formatted as a link when sending notifications of unanswered calls by email. The target will be specified in the href attribute of the introductory <a> tag. This target may be standardized with the help of a prefix. The following prefixes are available for pre-selection.

- **tel:** (Preset setting for Android, Blackberry and iOS, for example)
- **phone:**
- **callto:**

Furthermore, you have the option of assigning an individualized prefix (up to 9 characters plus colon). Note: the prefix must be terminated by a **colon**. If you do not want to use prefixes then disable this option. In that case, phone numbers will not be formatted as links in notification messages.

Exceptions

- **With internal calls**
No notifications are generated for internal calls.

- **Calls with hidden phone number**
No notifications are generated for calls with hidden numbers.
- **If no contact data could be found**
No notifications are generated for callers in which contact data couldn't be found.
- **With repeated phone calls on the same day**
If the caller makes more than one attempt on the same day, no notifications will be sent.
- **For phone calls repeated without user login**
If calls are made repeatedly and the user has not log into the system, for example, because they are on vacation.
- **If the call rang for less than 2 seconds**
If the caller rang for less than 2 seconds and you don't return calls from colleagues or customers who accidentally dialed your number.
- **If the calling number has been stored in this list**
Permit the exclusion of certain extensions or phone numbers from notifications. Such numbers may include, for example, the reception desk.

Use this language

You can set the language in which the e-mails are sent. The languages for which files exist in the *languages* directory are available.

6.9 E-Mail dispatch

estos ProCall Attendant Console supports sending email. This transmission feature is used for administrator error notifications and events, as well as for notifying users of unanswered calls.

SMTP server

Host name, or IP address and port number, for the mail server. By default, the port number will either be 25 (SMTP), 465 (SMTPS) and 587 (SUBMISSION). The TLS encryption will be used (except on port 25) if supported by the mailserv.

Login name (optional)

User name for the SMTP connection (SMTP AUTH)

Password (optional)

Password for the SMTP connection (SMTP AUTH)

Sender's e-mail address

The sender's e-mail address.

Recipient's e-mail address

The administrator's e-mail address for the delivery of error messages.
You may enter multiple addresses separated by a semi-colon.

Allow e-mails with UTF-8 (UNICODE) contents

Allows the server to send e-mails in UTF 8 code. If you deactivate this option, e-mails can send only characters known in the ISO Latin code page of the operating system.

Force TLS

Activates forced TLS encryption. If the server does not provide any encryption, transmission will fail.

Validate...

A test message will be sent, which may take a few minutes. A pop-up dialog will then appear, which will report on the success or failure (including potential error message) of the test.

6.10 SMS dispatch

estos ProCall Attendant Console can offer SMS dispatch using several providers. To use these services, you must be registered with one of the providers listed who will invoice you for this service. Fees may vary depending on the provider. With some providers you have to have a static IP in order to use the service. Simply compare the various providers and pick out the most favourable one for you.

Configuration

- Select one of the SMS providers listed.
- Enter the data specified by the provider into the field user name and password.
- Various providers allow the use of gateways to take advantage of certain features. A short text describes the individual gateways and their features.
- Depending on the provider, you can also include the return address with the query. If this option is offered by the provider, you can choose between three different ways of defining the return address. If you choose to use the mobile phone No. configured in the user profile, only those users having a mobile phone number may use the SMS function.
- Sending a test SMS permits you to test the configuration.



In principle, every service provider can be connected if it has a HTTP GET or POST interface. For this the configuration file has to be adapted accordingly in the installation list *config\smsprovider.xml*. The template can be found under *config\default\smsprovider.xml*.

6.11 XSL templates

The estos ProCall Attendant Console uses XSL Templates (short: XSLT) for the display of XML data as html sites. The XSL Template files are in the *Templates* or *Templates/default* directory.

Template	Deployment
<i>unanswered.xslt</i>	E-mail notification of unanswered or forwarded phone calls. View XSL templates for e-mail notification

XSLT processor

estos ProCall Attendant Console provides the data as XML files. These XML files are processed into an HTML page with the help of an XSL template and an XSLT processor. Either Sablotron or the Microsoft® XML Parser are used as an XSLT processor.

Development of own templates

You can develop and use your own templates. You should familiarise yourself with XSLT syntax for this. You can find help on the subject at SelfHTML or the Microsoft® MSDN pages.

If you wish to use templates you have developed yourself these should be stored in the *config* directory. Your changes will then not be lost if an product update is installed.

6.12 XSLT for e-mail notification

The *unanswered.xslt* file is used for e-mail notification of unanswered or forwarded calls.

The XML files on which the template is used are created by the ProCall Attendant Console. File *sample_unanswered.xml* contains example files for an unanswered call. File *sample_redirected.xml* contains example files for a forwarded call. The files are to be found in the *templates/default* directory.

You can use the *msxslt.exe* program supplied to apply an XSLT to an XML file. Open a command line in the installation directory:

```
msxslt.exe templates\default\sample_unanswered.xml
templates\default\unanswered.xslt -o unanswered.htm
```

If the logLevel is set under Events on debug, a XML file is provided in the list *logs* for every unanswered phone call. You can use this for the development of your own XSL templates.

6.13 Configuration file location

Location configuration

The configuration of the locations is always stored in an *xml* file. The file is in *config\locations.xml*.

Country dialing rules

The dialing rule table contains the country dialing rules. These are stored in the *countries.xml* file. It contains the names of the countries and the appropriate dialing rules for local, national and international calls.

```
<?xml version="1.0" encoding="UTF-8" standalone="no" ?>
<countries xmlns="http://www.w3.org/2001/XMLSchema.xsd">
<country ID="49">
<countryCode>49</countryCode>
<name>Germany</name>
<SameAreaRule>G</SameAreaRule>
<LongDistanceRule>oFG</LongDistanceRule>
<InternationalRule>ooEFG</InternationalRule>
</country>
</countries>
```

Icon	Meaning
E	Country code
F	Area code
G	Local number
I	Optional dialing code
N	Optional long distance provider

Call-by-call country dialing codes

The *providers.xml* file contains the known call-by-call dialing codes for individual countries.

```
<?xml version="1.0" encoding="UTF-8" standalone="no"?>
<providers xmlns="http://www.w3.org/2001/XMLSchema.xsd">
<provider ID="10???" countryID="41">
<name>General</name>
</provider>
<provider ID="10703" countryID="41">
```

```
<name>Smartphone</name>
</provider>
<provider ID="01090" countryID="49">
<name>O2</name>
</provider>
</providers>
```

Day	Meaning
countryID	ID of the country in countries.xml
ID	Provider dialing prefix (? is a place-holder for any digit)

Dialing codes and place names

The *cities.xml* file contains the known place names for the country dialing codes.

```
<?xml version="1.0" encoding="UTF-8" standalone="no"?>
<cities xmlns="http://www.w3.org/2001/XMLSchema.xsd">
<city ID="+1201" countryID="1">
<name>New Jersey</name>
</city>
<city ID="+4989" countryID="49">
<name>München</name>
</city>
</cities>
```

Day	Meaning
countryID	ID of the country in <i>countries.xml</i>
ID	Area code

Special phone numbers

The *specialnumbers.xml* file contains the known country special phone numbers. These are numbers which are not internationally dialable, e.g. emergency or information numbers. No dialing code is added to these numbers during formatting.

```
<?xml version="1.0" encoding="UTF-8" standalone="no"?>
<specialnumbers xmlns="http://www.w3.org/2001/XMLSchema.xsd">
<specialnumber ID="110" countryID="49">
<name>Notruf</name>
</specialnumber>
</specialnumbers>
```

Day	Meaning
countryID	ID of the country in countries.xml

ID	Phone number
----	--------------

6.13.1.1 Telephone number formats

Supercanonical number

A phone number format which allows the unique international identification of the participant. The estos UCServer and estos ProCall exclusively use the super-canonical phone number format for all phone numbers. For the display the simplified number is sometimes used (if available). Phone calls are carried out with the shortened phone number.

Supercanonical phone numbers always begin with a + and have the following format: **+Country City Number**

But no spaces are used. e.g. +49301234567

The number should only contain digits and +.

Service numbers

are special public phone numbers which cannot be given in international number format. These are for example emergency numbers (110) or directory enquiries (118xx). In order to be able to dial these numbers from a PC they must either be longer than the internal phone numbers or configured as external rules. these numbers are specified directly as dialable numbers:

DDI Phone number

Direct Dialling In phone number. External phone number of a participant in the system. This phone number can be displayed in its short form as well as in the international form bconsisting of country, dialing code and DDI. DDI numbers will be shown in short form for the same location, the system uses the international form internally.

Phone number

No spaces are used. Example: 11833

Dialable phone numbers

are always kept in the format required by the phone system in order to reach the subscriber. The number is formatted according to the rules in estos UCServer.

Examples:

Phone number internal extension number

Phone number external dialing code Number of subscriber 12345 in the local area network

External dialing code Country Area code Phone number Number of a subscriber in a different country

The above examples apply for Germany and depend to a large extent on the regions. You can see which dialing rules apply for your location in the location settings.

Phone numbers for display

are used by estos ProCall insofar as this form consisting of the country code and the area code can be determined.

+Country (area code) number

Example:

+49 (30) 123456 Phone number of subscriber 123456 in Berlin, Germany

6.14 Collaboration

In **Colaboration** the behavior of the client regarding chat from other estos ProCall Attendant Console users and notifications of presence changes of contacts are described.

- Chat
- Notification window

- Audio/Video Wizard

6.14.1 Chat

Display time without user interaction

If you didn't respond to a new chat, the chat window will be faded out after a specific time and a new chat will be added to the speech bubble info window. As soon as you respond to a chat message, the window will not be faded out automatically any more.

Transparency, support display and fading out

The chat window supports transparency and is generally faded in and out. If you do not wish to use this function, deactivate transparency.

Window position

You can determine where a message window opened by estos ProCall Attendant Console should be displayed.

- **Default position (task bar icon)**
ProCall Attendant Console opens the chat window to a suitable location on the screen. Other, already opened windows of ProCall Attendant Console are not superimposed.
- **Remember last position**
If you close a message window, the position is stored and displays new windows there.
- **Define position using preview**
Open a chat window with the button "Preview" and place this at the position where future windows are to be opened. As soon as you close the window, the position will be stored.
- **At mouse position**
The mouse cursor will be used as a reference position, so that the window will always appear in the immediate vicinity of the window(s) being used for work.



These settings do not apply for chats that have been started by the user. In this case, the message window will always be opened at the mouse position.

6.14.2 Notification window

Notification windows can draw the user's attention to certain presence changes of contacts in Favorites. These appear for specially selected user then a small notification window, in the short type of change is indicated and which contact is concerned.

Notification in case of the following event:

- **Contact becomes available.**
The notification window appears when a tagged contact logs on, switches from the status "Inactive" to "Available" or switches from "Absent" to "Available".
- **Contact signs out.**
The notification window indicates when a tagged contact signs out.
- **Contact has a call to pick up.**
The notification window appears when a call rings for the tagged contact while the tagged contact is not "available", but contact permits picking the call.

Display duration

The notification window will fade out after a certain time. With this setting, you can define the time period yourself.

Transparency, support display and fading out

The notification window supporty transparency and generally fades in and out. If you do not wish to use this function, deactivate transparency.

Window position

The position can be defined where a notification window opened by estos ProCall Attendant Console should be shown.

- **Default position (task bar icon)**
estos ProCall Attendant Console will open a new window at a appropriate position on the screen. Other already open windows of estos ProCall Attendant Console will not be overlaped.
- **Remember last position**
A notification window will appear at the same position where you have closed it or it was automatically hidden.
- **Define position using preview**
Open a notification window with the button "Preview" and position it where future windows are to be opened. Moving the message box has no effect on the display position.

6.14.3 Audio/Video Wizard

With the **initial startup** of the estos ProCall Attendant Console the user can decide if Audio and Video devices are to be used (for VideoChat and Audio applications), if Audio devices only are to be used (for AudioChat, Softphone, Bluetooth) or if no devices are to be used (Audio/Video off). The selected configuration can be changed later anytime by pressing the AV device item at the Presence area. If an Audio or Video device is configured to be used an Audio/Video Wizard starts.

During **normal operation** the Audio/Video Wizard opens automatically if the device configured for Audio/VideoChat is removed and if another device could be selected. If another device is configured the new one is further on used but the old one stays known. Thus, the previous settings remain known for laptops with docking stations and will be corresponding set in the event of changes to the docking state without intervention.

- **Audio configuration**
With the Audio Wizard the microphone and the speaker devices can be configured to be used with Audio/VideoChat. Pressing the "Devices" button opens the Windows® sound devices e.g. for configuring the Windows® standard devices or just for review. While the Wizard is open devices may be plugged in or removed. The list updates accordingly.
The use of USB headsets or Bluetooth / DECT headsets with USB dongle is recommended (see below the list of supported and tested devices). Otherwise the device control could not work or the presence (e.g. connected, on / off) of the device could not be recognized.
When using a Bluetooth headset directly coupled with the PC, the microphone and speaker devices should be set with the name "Hands Free AG Audio" in the device name. Bluetooth headsets also offer a speaker device with the name "Stereo" in the device name. This is only intended for music playback, because it is muted by the PC when "Hands Free AG Audio" devices are activated while having calls. If the connection status of a directly coupled Bluetooth headset changes, the device names are updated accordingly on the audio wizard. In some cases the microphone speech quality is improved when the "device echo cancellation" is deactivated (see below). It is recommended not to pair more than one Bluetooth audio device.

6.14.3.1 Device echo canceller

Most audio devices offer hardware echo cancellation with high quality (default on). If echo cancellation on the device is deactivated or not available, software echo cancellation (based on WebRTC) is used automatically. If hardware based echo cancellation is active and strange noises or unwanted blanking effects are heard from the other party (e.g., when both are speaking), the behavior may improve if the device echo canceller is disabled.

6.14.3.2 *Device automatic gain control*

Some audio devices offer a hardware-specific automatic gain control "AGC". If AGC is deactivated or not available on the device, a software AGD (WebRTC based) is automatically used. If the hardware-specific AGC interferes, it can be disabled here (Default setting on).

6.14.3.3 *Noise cancellation*

Sometimes the microphone is near a noise source, e.g. a built-in laptop microphone, air conditioner or fan is running. The voice quality can increase if noise reduction is activated in such environments (default setting off).

6.14.3.4 *Call control via audio device buttons*

If the selected device supports call control with device buttons (Human Interface Device "HID" buttons, e.g. for accepting or dropping calls) a checkbox "Enable Hook switch support" is offered (otherwise disabled grey). If the option is checked Audio/VideoChats can be accepted or dropped per device button. The list of supported HID devices can be found below. For example incoming Audio/Video chats are accepted and ended by the corresponding press of a button on the headset. Several phone calls can also be handled simultaneously. For example, if there is already a conversation, additional callers can be accepted by pressing a button. The existing conversation will be placed on hold.

Some devices (for example with a hands-free function) have separate buttons for accepting and ending calls. You can refuse a call with the End call button or accept a call with the Accept button. If the device offers a swap calls function, pressing the Answer button allows users to change between conversations. If the microphone was switched to Mute during a call, muting will be suspended when switching to another call. The list of supported audio devices with control options is at the bottom of this page.

In the case of the use of Plantronics headsets, please note that the "Plantronics Hub" software must be installed (for details, see below under Plantronics devices).



The test button offers a simple way to verify that your current device configuration is working with the software. After pressing the microphone test button a LED bar lits according to your speech for some seconds. After pressing the playback test button a sound is played for some seconds to the selected speaker device. Pressing the button again while the test runs cancels the test.

- **Video settings**

With the Video Wizard the camera device can be configured to be used with VideoChat. The actually selected camera starts immediately and a test picture is shown. This helps identifying the selected camera device and the camera can be adjusted before a VideoChat starts the first time.

If the selected camera device supports to be remote controlled per software the option "Enable remote control of the local camera" checkbox becomes enabled (otherwise disabled grey). If checked the local user can move the remote camera. The camera can be turned to the left (arrow key left), to the right (arrow key right), upwards (arrow key up) and downwards (arrow key down). Further it is possible to zoom-in (key "-") and to zoom-out (key "+"). The controlling user may also move the remote camera by using the mouse in the main Video picture with the related overlay buttons (see also Conversation window). The list of supported devices can be found below.

6.14.3.5 Audio/video hardware with control option

6.14.3.5.1 Logitech®:

Logitech® Hardware	Call control	Mute	LED	Camera control
USB Headset H570e Mono	yes	yes	yes	n/a
USB Headset H570e Stereo	yes	yes	yes	n/a
USB Headset H650e Mono	yes	yes	yes	n/a
USB Headset H650e Stereo	yes	yes	yes	n/a
USB DECT Headset H820e Mono	yes	yes	yes	n/a
USB DECT Headset H820e Stereo	yes	yes	yes	n/a
USB B530	yes	yes	no	n/a
USB Speakerphone P710e	yes, including swap calls	yes	yes	n/a
USB Camera BCC950	yes	yes	yes	yes
ConferenceCam CC3000e	yes, including swap calls	yes	yes	yes

6.14.3.5.2 Plantronics:

Calls can be controlled by Plantronics devices if the "Plantronics Hub" headset software was installed on the computer. This software comes provided on CD or can be downloaded from the manufacturer's web site. If an old version of "Plantronics Spokes" is installed, the current "Plantronics Hub" software must be installed. Use the Plantronics Hub software to adjust the behavior of Plantronics headsets. For example, the smart sensor can be set (if available), which accepts calls when the headset is donned and end calls when removed. Moreover, the automatic muting of the smart sensor can be adjusted there, which can be helpful in some situations, but also undesirable. The software can be opened via a Headset icon in the Windows® System-Tray (use the mouse on the icons of the taskbar). If a Bluetooth USB dongle was supplied with the headset, it should be used on the PC as otherwise the device controller may not function, for example.

Plantronics Hardware	Call control	Mute	LED	Sensor	Ringer
Blackwire C320	yes	yes	yes	no	no
Blackwire C325	yes	yes	yes	no	no
Blackwire C720 (USB)	yes	yes	yes	yes	no
Blackwire C720-M (USB)	yes	yes	yes	yes	no

Savi W440A (D100)	yes	yes	yes	no	yes
Savi 7xx	yes	yes	yes	no	yes
Voyager 5200 UC (BT600)	yes	yes	yes	yes	yes
Voyager Focus UC (BT600)	yes	yes	yes	yes	yes
Voyager Legend UC (BT300)	yes	yes	yes	yes	yes
Calisto 620 (BT300C)	yes	yes	yes	no	no
Encore Pro HW301N/A-DA45/A	yes	yes	only mute LED	no	no

Smart Sensor is a name of Plantronic for call control functionality (while putting on = accept call; while putting down = end call)
Intrusion Ringer describes a headset's own ringing sound for incoming calls.

6.14.3.5.3 Sennheiser:

The following headsets from the manufacturer have been successfully tested and are suitable for Call Control, other models from the manufacturer are available with Call Control.

Hardware	Call control
Circle SC 260 USB CTRL	yes
Century SC 630 USB CTRL	yes
DW Office	yes
DW Pro 1	yes
Presence UC	yes

6.14.3.5.4 Jabra™:

The following headsets from the manufacturer have been successfully tested and are suitable for Call Control, other models from the manufacturer are available with Call Control.

Hardware	Call control
Jabra™ Engage 75	yes
Jabra™ Evolve2 65	yes

Jabra Pro™ 9460 EMEA	yes
Jabra Evolve™ 65 UC Stereo	yes
Jabra™ BIZ 2400 II Mono USB	yes
Jabra™ SPEAK 510 UC	yes
Jabra™ SPEAK 710	yes
Jabra™ SPEAK 810	yes

6.14.3.5.5 Gigaset:

Hardware	Call control	Mute	LED
Gigaset ION	yes, including hold, swap calls and refuse calls	yes	yes

6.14.3.5.6 Yealink:

The following headsets from the manufacturer have been successfully tested and are suitable for Call Control, other models from the manufacturer are available with Call Control.

Hardware	Call control	Mute	LED
Yealink UH36	yes	yes	yes

6.14.3.5.7 Polycom®:

Other hardware	Call control	Mute	LED
Polycom® CX100	yes, including swap calls	yes	yes

6.14.3.6 Technical requirements for audio devices

The audio devices for softphones and audio / video chat are supported with sampling rates of 8 kHz ... 96 kHz, mono / stereo, in 16/24 bit PCM format. All devices in the system should be set in this ranges.

7 Info about estos ProCall Attendant Console

estos ProCall Attendant Console is a product of estos GmbH.

Copyright (C) 2023 estos GmbH.

For product updates visit <https://www.estos.de/>

Frequently asked questions and answers and also support are available at <https://support.estos.de>

Mac®, iPhone® are either registered trademarks or trademarks of Apple Inc., registered in the U.S. and other countries.

Jabra Evolve™, Jabra Pro™, Jabra™ are trademarks of GN Audio A/S and/or its affiliates (“GN Group”).

IBM Notes®, IBM®, Lotus® are either trademarks, common law marks or registered trademarks of IBM in the United States.

Logitech® is either a registered trademark or trademark of Logitech in the United States and/or other countries. All other trademarks are the property of their respective owners.

Active Directory®, Microsoft Access®, Microsoft Outlook®, Microsoft®, Outlook®, Windows® are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

Polycom®, Polycom® CX100 are trademarks in the United States and/or other countries.

MetaDirectory, ProCall are either registered products or products of estos GmbH in Germany and/or other countries.

Google is either a registered trademarks or trademark of Google Inc. in the U.S. and/or other countries.

All brands and product names used in this document are for identification purposes only and may be trademarks or registered trademarks of their respective owners.